

MUIbase

A relational programmable database
Version 4.0

10 October 2017

Steffen Gutmann

Copyright © 2017 Steffen Gutmann

Permission is granted to make and distribute verbatim copies of this manual provided the copyright notice and this permission notice are preserved on all copies.

Table of Contents

1	MUIbase Copying Conditions	1
1.1	License	1
1.2	Donation	1
1.3	Mailing List	1
1.4	Disclaimer	1
1.5	Third Party Material	1
1.5.1	Windows, Mac OS and Linux Versions	2
1.5.2	Amiga Version	2
2	Welcome to MUIbase	4
3	Getting Started	5
3.1	Installing MUIbase on Windows	5
3.2	Installing MUIbase on Mac OS	5
3.3	Installing MUIbase on Linux	5
3.4	Installing MUIbase on Amiga	6
3.5	Updating from a Previous Version	6
3.6	Starting MUIbase	6
3.7	Quitting MUIbase	7
3.8	Filename Conventions on Windows, Mac OS and Linux	7
4	Tutorial	9
4.1	How MUIbase Works	9
4.2	Starting with a Project, the Structure Editor	9
4.3	Adding a Table	9
4.4	Adding an Attribute	10
4.5	Displaying the Project	10
4.6	Adding two Reference Attributes	11
4.7	Adding Records	12
4.8	Filter	12
4.9	Queries	13
4.10	Adding a Table with a Memo and a Button Attribute	13
4.11	Programming MUIbase to do a Pedigree	14
4.12	Programming MUIbase to List a Person's Children	15
5	Basic Concepts	18
5.1	Projects	18
5.2	Tables	18
5.3	Records	19
5.4	Attributes	19
5.5	Attribute Types	19

5.5.1	String Attributes	19
5.5.2	Integer Attributes	20
5.5.3	Real Attributes	20
5.5.4	Boolean Attributes	20
5.5.5	Choice Attributes	20
5.5.6	Date Attributes	20
5.5.7	Time Attributes	20
5.5.8	Memo Attributes	21
5.5.9	Reference Attributes	21
5.5.10	Virtual Attributes	21
5.5.11	Buttons	21
5.6	Table of Attribute Types	22
5.7	Memory Consumption	22
5.8	Relationships	23
5.8.1	One to one Relationships	23
5.8.2	One to many Relationships	23
5.8.3	Many to many Relationships	24
5.9	User Interface	25
5.9.1	Windows	26
5.9.2	Masks	26
5.9.3	Panels	26
5.9.4	Attribute Objects	26
5.9.5	Text Objects	27
5.9.6	Images	27
5.9.7	Space Objects	27
5.9.8	Groups	27
5.9.9	Balance Objects	27
5.9.10	Register Groups	27
6	Managing Projects	28
6.1	File Format	28
6.2	Info	28
6.3	New Project	28
6.4	Clear Project	28
6.5	Open Project	29
6.6	Save Project	29
6.7	Admin and User Mode	30
6.8	Check Data Integrity	30
6.9	Swap Records	30
6.10	Close Project	31

7	Preferences	32
7.1	User Settings	32
7.1.1	Formats	32
7.1.2	External Editor	32
7.1.3	External Viewer	33
7.1.4	Extra Buttons in Tab Chain	33
7.1.5	Advance on Enter	34
7.1.6	Confirm Quit	34
7.1.7	MUI	34
7.2	Project Settings	34
7.2.1	Record Memory	34
7.2.2	Confirm Delete Record	35
7.2.3	Paths Relative to Project	35
7.2.4	Confirm Auto Reload	35
7.2.5	Confirm Save & Reorg	35
7.2.6	Program Source	35
7.2.7	Cleanup External Program Source	36
7.2.8	Program Debug Information	36
7.2.9	Obsolete Functions	36
7.2.10	Sort Trigger Functions	36
7.2.11	Program Include Directory	37
7.2.12	Program Output File	37
7.3	Save as Default	37
8	Log	38
8.1	Log Table	38
8.2	Activate Logging	38
8.3	Set Log Label	39
8.4	Import Log	39
8.5	Export Log	39
8.6	Clear Log	39
8.7	View Log	39
9	Record-Editing	40
9.1	Active Object	40
9.2	Adding Records	40
9.3	Changing Records	40
9.3.1	String Attributes with Pop-up Button	40
9.3.2	Entering Integer Values	41
9.3.3	Entering Boolean Values	41
9.3.4	Entering Choice Values	41
9.3.5	Entering Date Values	41
9.3.6	Entering Time Values	41
9.3.7	Memo Context Menu	41
9.3.8	Select-from-where List Context Menu	42
9.3.9	Entering Reference Values	42
9.3.10	Entering NIL Value	42

9.4	Deleting Records	42
9.5	Browsing Records	43
9.6	View all Records	43
10	Filter	44
10.1	Record Filter	44
10.1.1	Filter Expression	44
10.1.2	Changing Filters	44
10.1.3	Filter Examples	45
10.2	Reference Filter	45
11	Order	46
11.1	Empty Order	46
11.2	Order by Attributes	46
11.3	Order by a Function	47
11.4	Changing Orders	47
11.5	Reorder all Records	48
12	Search For	49
12.1	Search Dialog	49
12.2	Forward/Backward Search	49
12.3	Search Pattern Examples	50
13	Import and Export	51
13.1	File Format	51
13.2	Sample Import File	51
13.3	Importing Records	52
13.4	Exporting Records	52
14	Data Retrieval	53
14.1	Select-From-Where Queries	53
14.2	Query Editor	53
14.3	Exporting Queries as Text	54
14.4	Exporting Queries as PDF	55
14.5	Printing Queries	55
14.6	Query Examples	56

15	Structure Editor	59
15.1	Table Management	59
15.1.1	Creating Tables	59
15.1.2	Changing Tables	60
15.1.3	Deleting Tables	60
15.1.4	Sorting Tables	60
15.2	Attribute Management	60
15.2.1	Creating Attributes	61
15.2.2	Type Specific Settings	61
15.2.3	Label Editor	62
15.2.4	Copying Attributes	63
15.2.5	Changing Attributes	63
15.2.6	Deleting Attributes	63
15.2.7	Sorting Attributes	64
15.3	Display Management	64
15.3.1	Display Field	64
15.3.2	Table Object Editor	65
15.3.3	Attribute Object Editor	66
15.3.4	Type Specific Settings	67
15.3.5	Text Editor	70
15.3.6	Image Editor	71
15.3.7	Space Editor	71
15.3.8	Group Editor	71
15.3.9	Register Group Editor	72
15.3.10	Window Editor	72
15.4	Export Structure	73
16	Programming MUIbase	74
16.1	Program Editor	74
16.2	External program source	74
16.3	Preprocessing	75
16.3.1	#define	75
16.3.2	#undef	75
16.3.3	#include	75
16.3.4	#if	76
16.3.5	#ifdef	76
16.3.6	#ifndef	76
16.3.7	#elif	76
16.3.8	#else	77
16.3.9	#endif	77
16.4	Programming Language	77
16.4.1	Why Lisp?	77
16.4.2	Lisp Syntax	77
16.4.3	Kinds of Programs	78
16.4.4	Name Conventions	78
16.4.5	Accessing Record Contents	78
16.4.6	Data Types for Programming	79

16.4.7	Constants	80
16.4.8	Command Syntax	81
16.5	Defining Commands	81
16.5.1	DEFUN	81
16.5.2	DEFUN*	82
16.5.3	DEFVAR	82
16.5.4	DEFVAR*	83
16.6	Program Control Functions	83
16.6.1	PROGN	83
16.6.2	PROG1	83
16.6.3	LET	83
16.6.4	SETQ	84
16.6.5	SETQ*	84
16.6.6	FUNCALL	85
16.6.7	APPLY	85
16.6.8	IF	85
16.6.9	CASE	85
16.6.10	COND	86
16.6.11	DOTIMES	86
16.6.12	DOLIST	87
16.6.13	DO	87
16.6.14	FOR ALL	88
16.6.15	NEXT	88
16.6.16	EXIT	88
16.6.17	RETURN	89
16.6.18	HALT	89
16.6.19	ERROR	89
16.7	Type Predicates	89
16.8	Type Conversion Functions	90
16.8.1	STR	90
16.8.2	MEMO	91
16.8.3	INT	91
16.8.4	REAL	92
16.8.5	DATE	92
16.8.6	TIME	93
16.9	Boolean Functions	93
16.9.1	AND	93
16.9.2	OR	94
16.9.3	NOT	94
16.10	Comparison Functions	94
16.10.1	Relational Operators	94
16.10.2	CMP	95
16.10.3	CMP*	95
16.10.4	MAX	95
16.10.5	MAX*	95
16.10.6	MIN	96
16.10.7	MIN*	96
16.11	Mathematical Functions	96

16.11.1	Adding Values	96
16.11.2	Subtracting Values	97
16.11.3	1+	97
16.11.4	1-	97
16.11.5	Multiplying Values	97
16.11.6	Dividing Values	97
16.11.7	DIV	98
16.11.8	MOD	98
16.11.9	ABS	98
16.11.10	TRUNC	98
16.11.11	ROUND	98
16.11.12	RANDOM	98
16.11.13	POW	99
16.11.14	SQRT	99
16.11.15	EXP	99
16.11.16	LOG	99
16.12	String Functions	99
16.12.1	LEN	100
16.12.2	LEFTSTR	100
16.12.3	RIGHTSTR	100
16.12.4	MIDSTR	100
16.12.5	SETMIDSTR	100
16.12.6	INSMIDSTR	101
16.12.7	INDEXSTR	101
16.12.8	INDEXSTR*	101
16.12.9	INDEXBRK	101
16.12.10	INDEXBRK*	101
16.12.11	RINDEXSTR	101
16.12.12	RINDEXSTR*	102
16.12.13	RINDEXBRK	102
16.12.14	RINDEXBRK*	102
16.12.15	REPLACESTR	102
16.12.16	REPLACESTR*	102
16.12.17	REMCHARS	103
16.12.18	TRIMSTR	103
16.12.19	WORD	103
16.12.20	WORDS	103
16.12.21	FIELD	104
16.12.22	FIELDS	104
16.12.23	STRTOLIST	104
16.12.24	LISTTOSTR	105
16.12.25	CONCAT	105
16.12.26	CONCAT2	105
16.12.27	COPYSTR	105
16.12.28	SHA1SUM	106
16.12.29	UPPER	106
16.12.30	LOWER	106
16.12.31	ASC	106

16.12.32	CHR	106
16.12.33	LIKE	107
16.12.34	SPRINTF	107
16.13	Memo Functions	109
16.13.1	LINE	109
16.13.2	LINES	109
16.13.3	MEMOTOLIST	110
16.13.4	LISTTOMEMO	110
16.13.5	FILLMEMO	110
16.13.6	FORMATMEMO	111
16.13.7	INDENTMEMO	111
16.14	Date and Time Functions	111
16.14.1	DAY	111
16.14.2	MONTH	111
16.14.3	YEAR	111
16.14.4	DATEDMY	112
16.14.5	MONTHDAYS	112
16.14.6	YEARDAYS	112
16.14.7	ADDMONTH	112
16.14.8	ADDYEAR	113
16.14.9	TODAY	113
16.14.10	NOW	113
16.15	List Functions	113
16.15.1	CONS	113
16.15.2	LIST	114
16.15.3	LENGTH	114
16.15.4	FIRST	114
16.15.5	REST	114
16.15.6	LAST	114
16.15.7	NTH	114
16.15.8	APPEND	115
16.15.9	REVERSE	115
16.15.10	MAPFIRST	115
16.15.11	SORTLIST	115
16.15.12	SORTLISTGT	116
16.16	Input Requesting Functions	116
16.16.1	ASKFILE	116
16.16.2	ASKDIR	116
16.16.3	ASKSTR	117
16.16.4	ASKINT	117
16.16.5	ASKCHOICE	117
16.16.6	ASKCHOICESTR	118
16.16.7	ASKOPTIONS	119
16.16.8	ASKBUTTON	119
16.16.9	ASKMULTI	120
16.17	I/O Functions	121
16.17.1	FOPEN	121
16.17.2	FCLOSE	122

16.17.3	stdout	122
16.17.4	PRINT	123
16.17.5	PRINTF	123
16.17.6	FPRINTF	123
16.17.7	FERROR	123
16.17.8	FEOF	124
16.17.9	FSEEK	124
16.17.10	FTELL	124
16.17.11	FGETCHAR	124
16.17.12	FGETCHARS	124
16.17.13	FGETSTR	125
16.17.14	FGETMEMO	125
16.17.15	FPUTCHAR	125
16.17.16	FPUTSTR	125
16.17.17	FPUTMEMO	125
16.17.18	FFLUSH	126
16.18	Record Functions	126
16.18.1	NEW	126
16.18.2	NEW*	126
16.18.3	DELETE	126
16.18.4	DELETE*	127
16.18.5	DELETEALL	127
16.18.6	GETMATCHFILTER	127
16.18.7	SETMATCHFILTER	128
16.18.8	GETISSORTED	128
16.18.9	SETISSORTED	128
16.18.10	RECNUM	128
16.18.11	COPYREC	129
16.19	Attribute Functions	129
16.19.1	ATTRNAME	129
16.19.2	MAXLEN	129
16.19.3	GETLABELS	129
16.19.4	SETLABELS	130
16.20	Table Functions	130
16.20.1	TABlename	130
16.20.2	GETORDERSTR	130
16.20.3	SETORDERSTR	130
16.20.4	REORDER	131
16.20.5	REORDERALL	131
16.20.6	GETFILTERACTIVE	132
16.20.7	SETFILTERACTIVE	132
16.20.8	GETFILTERSTR	132
16.20.9	SETFILTERSTR	132
16.20.10	RECORDS	133
16.20.11	RECORD	133
16.20.12	SELECT	133
16.21	GUI Functions	134
16.21.1	SETCURSOR	134

16.21.2	SETBGPEN	134
16.21.3	GETWINDOWOPEN	134
16.21.4	SETWINDOWOPEN	135
16.21.5	GETVIRTUALLISTACTIVE	135
16.21.6	SETVIRTUALLISTACTIVE	135
16.22	Project Functions	135
16.22.1	PROJECTNAME	135
16.22.2	PREPARECHANGE	136
16.22.3	CHANGES	136
16.22.4	GETADMINMODE	136
16.22.5	SETADMINMODE	136
16.22.6	ADMINPASSWORD	137
16.23	System Functions	137
16.23.1	EDIT	137
16.23.2	EDIT*	137
16.23.3	VIEW	137
16.23.4	VIEW*	137
16.23.5	SYSTEM	138
16.23.6	SYSTEM*	138
16.23.7	STAT	138
16.23.8	TACKON	138
16.23.9	FILENAME	139
16.23.10	DIRNAME	139
16.23.11	MESSAGE	139
16.23.12	COMPLETEMAX	139
16.23.13	COMPLETEADD	140
16.23.14	COMPLETE	140
16.23.15	GC	140
16.23.16	PUBSCREEN	140
16.24	Pre-Defined Variables	141
16.25	Pre-Defined Constants	141
16.26	Functional Parameters	142
16.27	Type Specifiers	142
16.28	Semantics of Expressions	143
16.29	Function Triggering	144
16.29.1	onOpen	144
16.29.2	onReload	144
16.29.3	onClose	145
16.29.4	onAdminMode	145
16.29.5	onChange	145
16.29.6	logLabel	146
16.29.7	mainWindowTitle	146
16.29.8	New Trigger	146
16.29.9	Delete Trigger	147
16.29.10	Comparison Function	147
16.29.11	Attribute Trigger	148
16.29.12	Programming Virtual Attributes	149
16.29.13	Compute Enabled Function	149

16.29.14	Compute Record Description	150
16.29.15	Double Click Trigger	150
16.29.16	Compute Listview Labels	151
16.29.17	Compute Reference Records	151
16.30	List of Obsolete Functions	151
17	ARexx Interface	153
17.1	Port Name	153
17.2	Command Syntax	153
17.3	Return Codes	154
17.4	Quit	155
17.5	Hide	155
17.6	Show	155
17.7	Info	155
17.8	Help	155
17.9	Compile	155
17.10	Connect	156
17.11	Disconnect	156
17.12	Connections	157
17.13	Eval	157
17.14	Transaction	158
17.15	Commit	158
17.16	Rollback	159
Menus	160
Menu Project	160
Menu Preferences	161
Menu Log	162
Menu Table	162
Menu Program	163
Menu Help	163
Acknowledgments	164
Author	165
Function Index	166
Concept Index	169

1 MUIbase Copying Conditions

MUIbase is Copyright © 1998-2017 Steffen Gutmann. All rights reserved.

MUIbase is open source software distributed under the terms of the GNU General Public License (GPL).

1.1 License

This program is free software: you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation, either version 3 of the License, or (at your option) any later version.

This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with this program. If not, see <http://www.gnu.org/licenses/>.

1.2 Donation

MUIbase is completely free of charge. However, if you like the project and would like to support it then you are welcome to make a donation. For making your donation please visit <http://www.sourceforge.net/projects/muibase/donate>.

1.3 Mailing List

A mailing list for discussion of MUIbase-related issues has been setup under <http://www.groups.yahoo.com/groups/muibase-list>. Everybody is welcome to join. Please send bug reports or feature requests to this mailing list.

1.4 Disclaimer

THIS SOFTWARE IS PROVIDED BY THE AUTHOR AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

1.5 Third Party Material

MUIbase uses external libraries and other material depending on the operating system.

1.5.1 Windows, Mac OS and Linux Versions

MUIbase 3.x for Windows, Mac OS and Linux uses the Gimp Toolkit (GTK+) version 2.10 or higher, copyright © 2007-2017 The GTK+ Team. GTK is a toolkit for developing graphical user interfaces (GUI) and is distributed under the GNU Library General Public License (LGPL). For more information, see <http://www.gtk.org>.

MUIbase 4.x for Windows, Mac OS and Linux uses Qt version 5.3 or higher, copyright © 2017 The Qt Company. Qt is a comprehensive cross-platform framework and toolkit available under GPL & LGPLv3 licenses. For more information, see <http://www.qt.io>.

The Windows install script for MUIbase is based on the install script for The Gimp which is copyright by Jernej Simoncic.

1.5.2 Amiga Version

The Amiga version of MUIbase uses

MUI - MagicUserInterface

Copyright © 1992-2013 Stefan Stuntz

MUI is a system to generate and maintain graphical user interfaces. With the aid of a preferences program, the user of an application has the ability to customize the outfit according to his personal taste.

MUI is distributed as shareware. To obtain a complete package containing lots of examples and more information about registration please look for a file called "muiXXusr.lha" (XX means the latest version number) on your local bulletin boards or on public domain disks.

If you want to register directly, feel free to send

DM 30.- or US\$ 20.-

to

Stefan Stuntz
Eduard-Spranger-Straße 7
80935 München
GERMANY

Support and online registration is available at

<http://www.sasg.com/>

MUIbase for Amiga uses NList.mcc, copyright © 2001-2015 NList Open Source Team. See <http://www.sourceforge.net/projects/nlist-classes> for more info or latest version.

MUIbase for Amiga uses BetterString.mcc, copyright © 2005-2015 BetterString Open Source Team. See <http://www.sourceforge.net/projects/bstring-mcc> for more info or latest version.

MUIbase for Amiga uses TextEditor.mcc, copyright © 2005-2015 TextEditor Open Source Team. See <http://www.sourceforge.net/projects/texteditor-mcc> for more info or latest version.

MUIbase for Amiga uses codesets.library, copyright © 2005-2015 codesets.library Open Source Team. See <http://www.sourceforge.net/projects/codesetslib> for more info or latest version.

Some icons used in the MUIbase for Amiga distribution are from the DefaultIcons set and are copyright © Michael-Wolfgang Hohmann and Angela Schmidt.

2 Welcome to MUIbase

MUIbase is a fast and flexible database system with graphical user interface (GUI) and programmability. It is targeted for advanced desktop users who want to manage data in a comfortable and powerful way. MUIbase is able to manage any kind of data, e.g. addresses, CD series, movies, photo collections, your family tree, your income and expense, and much more. The power of MUIbase lies in its clear and powerful graphical user interface and its programming capabilities. Programming MUIbase allows you to process data in various ways, e.g. automatic calculations upon user input, generation of reports, import and export of data, etc. For example it can be used for calculating the total amount of income, or the total amount of recorded time on a CD, or to automatically create and print serial letters to your customers.

MUIbase offers the following features:

- Shared access to a project from multiple instances of MUIbase running on the same or different computers.
- Unlimited number of projects, tables, attributes, and records.
- Attributes can be of type string, memo (multi line text), integer, real, date, time, boolean, choice (one item out of many items), reference (easy way to reference a record of another table), button (for starting MUIbase programs), and virtual (compute value on the fly).
- The string type can also manage lists of strings, files, and fonts. A string can refer to an external image which is displayed in the graphical user interface.
- Dynamic loading of records. Records which are not needed may be flushed from memory (e.g. when memory is low).
- Programmability. With the easy and powerful MUIbase programming language complex tasks can be implemented. The language also includes a SELECT FROM WHERE query for comfortable and fast data retrieval.
- Ordering of records by any combinations of attributes.
- Flexible and powerful search and filter facility.
- Query editor which allows entering and managing of SELECT FROM WHERE queries. The queries can be saved and the results can be printed.
- Optional logging of changes (adding, deleting and changing of records) into a system log table.
- Import and export facility.
- Full documentation including user and programming manual in HTML and PDF (plus AmigaGuide on the Amiga).
- The Amiga version provides a powerful ARexx interface for accessing MUIbase from other programs. The ARexx interface offers a transaction mechanism similar to other relational databases.
- Operating system independence. MUIbase is available for Windows, Mac OS, Linux and Amiga. The source code is available as part of a SourceForge project.

3 Getting Started

This chapter describes what the hardware and software requirements are to run MUIbase on your computer, the procedure for installing and updating MUIbase, and how to start and quit MUIbase.

3.1 Installing MUIbase on Windows

MUIbase 3.x for Windows runs on Intel compatible computers that use the Windows 2000, Windows XP, Windows Vista, Windows 7, Windows 8 or Windows 10 operating system. Starting with MUIbase version 4.0, Windows 7 or better is required.

The MUIbase installer is distributed as a Windows executable, e.g. ‘MUIbase-4.0-setup.exe’ which you can download from the MUIbase home page <http://muibase.sourceforge.net>. When running the installer, you will be asked several options about where to install MUIbase and which configuration to use. In case you have a previous MUIbase version installed on your computer, the installation procedure allows to update it to the new version.

After a successful installation your Windows ‘Start’ menu should contain a new entry for launching MUIbase. You can now remove the MUIbase installer as it is no longer needed.

3.2 Installing MUIbase on Mac OS

MUIbase for Mac OS supports Mac OS X Lion (10.7) and later versions of the Mac OS X operating system. The software is distributed as a 64bit Intel binary.

A disk image of MUIbase, e.g. ‘MUIbase-4.0-Lion.dmg’ can be downloaded from the MUIbase home page <http://muibase.sourceforge.net>. After downloading and opening the image, drag and drop ‘MUIbase.app’ into your computer’s ‘Applications’ folder.

3.3 Installing MUIbase on Linux

You can install and run MUIbase on an Intel-compatible computer running the Linux operating system.

MUIbase for Linux is distributed both, as a Debian package (e.g. ‘muibase_4.0_ubuntu_trusty_amd64.deb’ for Ubuntu or Debian) and as an RPM archive (e.g. ‘MUIbase-4.0-fc21.x86_64.rpm’ for Fedora).

There are separate versions for the 32bit architecture, e.g. ‘muibase_4.0_ubuntu_trusty_i386.deb’ and ‘MUIbase-4.0-fc21.i686.rpm’. All versions can be downloaded from the MUIbase home page <http://muibase.sourceforge.net>.

Usually MUIbase installs or updates itself automatically after downloading it on your computer. In case the installation process does not start automatically, the following commands executed as super user (root) in a command shell install or update MUIbase on a Debian-based Linux computer:

```
dpkg --install muibase.deb
apt-mark hold muibase.deb
```

where *muibase.deb* is the downloaded MUIbase Debian package.

On a Redhat-based system (RPM), the commands are:

```
rpm -Uvh MUIbase.rpm
```

where *MUIbase.rpm* is the downloaded RPM archive.

After a successful installation you should see a new menu item in the ‘Applications - Office’ menu tree of your (Gnome or KDE) desktop. At this time the downloaded archive is no longer necessary and can be removed.

NB: On Debian-based systems you need to hold the package otherwise the next update of your system will remove it because it’s not installed from a source defined in the repository list `/etc/apt/source.list`.

3.4 Installing MUIbase on Amiga

MUIbase for Amiga runs on Amiga OS version 3.0 or higher and requires an 68020 processor or better. Furthermore, MUI version 3.8 or higher must be present on your system. A minimum of 4MB RAM and 10MB of free hard disk space are needed. The m68k binary of MUIbase for Amiga has been reported to run stable on UAE, MorphOS and Amiga OS4. PowerPC binaries for MorphOS and Amiga OS4 are also available as part of the distributed archive. A separate distribution contains an AROS version.

MUIbase is distributed as an lha archive, e.g. ‘*MUIbase-3.0.lha*’ and can be downloaded from the MUIbase home page <http://muibase.sourceforge.net>. In order to install MUIbase on your computer unpack this archive to a temporary directory. Do not unpack it to the target directory!

Double click the MUIbase installer script `Install-MUIbase` and follow its instructions. The script asks for a directory where the software should be copied to. Do not enter the directory where you have unpacked the MUIbase archive to. The script is also capable of updating an existing MUIbase installation by entering the directory where you previously installed MUIbase.

After successful installation you will find a (new) drawer on your system containing the MUIbase program along with all necessary files and some sample projects. In addition an assign `MUIbase:` referring to this drawer has been added to your system file `S:User-Startup`. It is safe to remove the lha archive and the temporary files as they are no longer needed.

3.5 Updating from a Previous Version

When installing MUIbase, you can upgrade from a previous version of MUIbase or reinstall it as described above. During the new installation, all necessary files are replaced by new ones. This includes the sample projects in the `Demos` directory. It is therefore not recommended to place your own projects into this directory nor to use any of the sample projects for managing your own data as they are overwritten when reinstalling or upgrading MUIbase.

The recommended way to manage your own projects is to place them into a separate directory independent of the MUIbase installation directory.

3.6 Starting MUIbase

MUIbase can be started either from your graphical environment or from a command shell. On Windows you find MUIbase under the ‘Start’ menu. On Mac OS, you launch MUIbase

using ‘Finder’ from the ‘Applications’ directory. If you are running Gnome or KDE on Linux, you can start MUIbase by choosing the corresponding item from the ‘Applications - Office’ menu. On the Workbench (Amiga) you double click the MUIbase icon or the icon of a MUIbase project which is then automatically loaded after starting MUIbase (you can also select several MUIbase projects by shift clicking them and double clicking the last one).

When starting MUIbase from a command shell on Windows, Linux or Amiga you can include command line arguments and optional projects to load. There are two basic ways to start MUIbase from a command shell:

```
MUIbase [project1 ...]  
MUIbase -n
```

The first form starts MUIbase and loads the optional projects specified by their filenames *project1* The second form starts MUIbase without graphical user interface. This can be useful for running MUIbase as a server in the background and accessing it through its external interface (e.g. ARexx on Amiga, see Chapter 17 [ARexx interface], page 153).

3.7 Quitting MUIbase

To quit MUIbase select menu item ‘Project - Quit’ or close all opened projects.

3.8 Filename Conventions on Windows, Mac OS and Linux

MUIbase for Windows, Mac OS and Linux has a few special conventions for filenames that are usually not found in other software on those systems.

When MUIbase is starting, an environment variable ‘MUIbase’ is set referring to the installation directory of MUIbase. On Windows this is the directory specified during the software installation. On Mac OS, it is directory ‘/Applications/MUIbase.app/Contents/Resources/share/MUIbase’. On Linux, it is directory /usr/share/MUIbase.

When interpreting filenames (either entered by the user or the filenames present in this documentation) a filename is examined for the occurrence of environment variables. If a filename contains a dollar sign ‘\$’ then the characters following it until the first non-alpha-numeric character are interpreted as an environment variable and, if the environment variable is set, the part of the filename is replaced by the contents of the environment variable (otherwise the part of the filename is left unchanged including the ‘\$’ sign). You can use parentheses around the environment variable if it contains non-alpha-numeric characters. For example \$HOME/data expands to the path where \$HOME has been replaced with the path name of your home directory.

Furthermore, Amiga-style ‘assign names’ are handled in the following way. If a filename contains a colon ‘:’ then everything before the colon is treated like an environment variable (called ‘assign name’) and is replaced by its contents if the environment variable is set. ‘Assign names’ should be at least 2 characters in length, in order to distinguish them from drive letters on Windows.

These conventions allow, for example, to refer to the movie sample database inside the MUIbase installation directory as MUIbase:demos/Movie.mb.

Another example is when you set an environment variable, say `'EXTERNAL_DATA'`, referring to the directory where you store external data like images, etc. of one of your projects. You can then access data inside this directory through `EXTERNAL_DATA:some-file` and store such filenames in the database project.

4 Tutorial

The making of a family-tree database.

This chapter contains a brief tutorial describing the basic usage of MUIbase. Within the tutorial a small project is developed that allows the managing of your family tree. The project that results after applying all steps in this tutorial can be found as the 'FamilyTree.mb' project located in the Demos directory of your MUIbase installation.

4.1 How MUIbase Works

MUIbase could be said to operate in two different modes, record-editing and structure-editing mode.

The record-editing mode is where you add, change, or delete records.

The structure-editing mode lets you edit how your database should look like and what tables and attributes it contains.

Besides this there is the program editor where you enter program functions that are executed automatically when entering data or explicitly when pressing a program button.

4.2 Starting with a Project, the Structure Editor

To create a database you first need to define it's contents. In MUIbase this is done in the structure editor which is opened by choosing 'Structure editor' in the 'Project' menu. Here you find three different sections:

'Tables' Add, change, or delete the tables of your project.

'Attributes'
Add, change, or delete attributes of the currently selected table.

'Display' Specify the graphical layout of your database, i.e. how it should be displayed.

4.3 Adding a Table

First we need a table, press the 'New' button just below the list view in the 'Table' section. You will then see a dialog which asks you to enter some data:

'Name' The name of the table. The name must begin with an uppercase letter and can consist of up to 20 characters. The name can be changed later. In this tutorial we set the name to 'Person' since it's going to hold all the person's names in this database.

'Number of records'
A table can either consist of only one or of an unlimited number of records. In our case it should be set to unlimited since we are going to add more than one person.

'Trigger functions'
The adding and deletion of records can be controlled by program functions. This is where you set which function to call. Since we don't have written any program functions yet, we leave the fields empty.

When this is done, just press the 'OK' button and we have our first table, 'Person'.

4.4 Adding an Attribute

Then we need a string attribute for that table, press ‘New’ in the attributes section. Attributes also need some settings:

- ‘Name’ The same as for a table: first letter must be uppercase and altogether a maximum of 20 characters. We set the name of this attribute to ‘Name’ as it will contain the names of the persons we are about to add.
- ‘Type’ Here we choose what type this attribute should be. There are a couple of different ones but for this attribute we use a string attribute.
- ‘Max length’ Here you can define the maximum number of characters a user can enter for the string. We set this to 30.
- ‘Initial value’ It’s possible to have some attributes to use an initial value for every new record you add, here is where you enter what it should contain. Leave this line blank.
- ‘Trigger’ An attribute could also trigger a program function to be executed. For example, if you enter a name then you can have a program to check if this name already exists. We leave this field empty.

4.5 Displaying the Project

After pressing ‘OK’ you now should notice some changes in the display section. Change the choice button on the top of the display section to ‘Main window’. There you see what the main window holds, currently only table ‘Person’. If you change the choice button back to ‘Table mask’, you can see how table ‘Person’ is presented. Currently it’s displayed as one panel with one attribute.

Now double-click on ‘Person’ at the top of the list in the display section and a window should appear. Click on the ‘Panel’ tab and you can set how the panel of the table should be displayed:

- ‘Title’ The title of a table can be different to it’s name. Our table is called ‘Person’ but here we could set it to be ‘THIS IS THE TABLE PERSON!’ if we prefer that better.
 - ‘Background’ The background can be changed to whatever suits your taste.
 - ‘Gadgets’ Here we can define what gadgets we want the panel to have.
- Press ‘OK’ and then double-click on ‘Name’ in the list-view in the display section. This brings up the window that contains the settings for how to display the string attribute ‘Name’.

- ‘Title’ The same as for the panel. The string you enter here is what is really displayed when in record-editing mode.
- ‘Shortcut’ Here you can set a letter that can be used to jump to this attribute, when in record-editing mode. For jumping to the attribute you need to hold down the

Alt key (Windows, Mac OS and Linux) respectively the *Amiga* key and then press the letter.

'Home' Makes the cursor to jump to this attribute whenever a new record is added. In our case we will always or most of the time enter the name first in a new record, so set it.

'Read only' Set this if the attribute should be read only. Leave it unset.

'Weight' Decides how much of this attribute should be visible when competing for the space with other attributes. For example, if three 50-character strings resides in a window that only has room for 100 characters, then this number decides how much space the string gets relatively to the other ones. Leave it at 100.

'Background' The same as for the panel.

'Bubble help' Here you enter any text you think would be helpful to the user. The bubble help appears after holding the mouse still over an attribute for some seconds. Set this to **'If you need help, call the author at 112'**.

Leave the structure editor (choose **'Exit structure editor'** in the **'Project'** menu) and you are back to record-editing mode where you see how the database really looks like. You'll see the headline which is the string you may have entered in the display section for the panel. The record counter should say **'#0/0'** since we haven't added any records yet. Thereafter is a filter button and two arrow buttons. Below all this you should have the **'Name'** attribute with the text you may have entered in the display section for this attribute. If you haven't changed any text at all when in the display section then the panel should be named **'Person'**, and the string attribute **'Name'**. Move the mouse above the string attribute **'Name'** and leave it there for a couple of seconds. If you entered something in the bubble help above then this text should appear in a popup window.

4.6 Adding two Reference Attributes

Now we will add two reference attributes. Reference attributes are a bit different than other attributes. As their name might imply they refer to records. This will become more understandable as you try it out for yourself in just a while.

Enter the structure editor again and add two more attributes to table **'Person'**. Press **'New'** in the attributes section, name it **'Father'**, and change its type to **'Reference'**. A reference attribute has only one setting:

'Set reference to' Tells which table the attribute refers to. It should already be pointing to table **'Person'**. Leave it that way and press **'Ok'**.

Add another attribute by pressing **'New'** in the attribute section and call it **'Mother'**. The attribute's type should also be set to reference and point to table **'Person'**.

As you may have noticed, there are now three attributes in the display section. Click on **'Father'** and then on the buttons up and down located just to the left. This will change

where **Father** is positioned when looking at it while in record-editing mode. Put **Father** at the top, **Name** in the middle, and **Mother** at the bottom.

Next, we specify what contents the reference attributes **Father** and **Mother** should display from the referenced records. Double-click on **Father** in the display section and then click on **Extras**. Here we choose to display the string attribute **Name**, then we press **Ok** and repeat the procedure for **Mother**.

4.7 Adding Records

Now we should add some records. Leave the structure editor and enter record-editing mode. To add a new record you choose **New record** from the **Table** menu (on Windows and Linux you find this menu by pressing and holding the right mouse button inside the table mask). The cursor should now automatically jump to the attribute we have set to **Home** earlier in the display section in the structure editor. Add two records, one with your fathers name in **Name** and another one with your mothers name in **Name**. Thereafter you add another record with your own name in **Name**.

Now it's time to understand those reference attributes. By pressing on the list-view button on **Father** we get a list of all records this reference attribute could refer to. Choose your fathers name and do accordingly down below on the mothers list-view.

Now you should have three records, you, your father and your mother. In your record, your fathers name should be visible in **Father** at the top and your mothers name should be in **Mother** at the bottom. You can browse through the records by pressing **Alt** together with the cursor keys *Up* and *Down*.

But hey! My parents also has/had parents you say! So let's add another four records, the third generation. Just add the records one by one and write their names in **Name**. If you don't remember their names then just enter **father's father**, **mother's father** or something like that instead. Then you browse through all the records and set **Father** and **Mother** to what they should contain. When this is done you should have at least seven records, your record, your parents records and your grandparents records.

4.8 Filter

Since we now have some records to work with, we could try out the filter function. The filter can sort out records you don't want to display, they will still remain in the database but they are just not displayed anymore.

To edit the filter you choose **Change filter** from the **Table** menu. A window with loads of operators will appear. This is where you set what conditions a record must fulfill to get displayed.

In this small example we will use the **LIKE** command, which lets you do a joker comparison of an attribute. Press once on the **LIKE** button to the right and then double-click on **Name** in the list to the left and (**LIKE Name**) should appear in the string just above the **Ok** and **Cancel** buttons. Thereafter you type **"*a*"** so the whole string shows (**LIKE Name "*a*"**). This means that MUIbase should display all records that contain the letter **'a'** anywhere in **Name**.

Press 'Ok' and you may notice that records with no 'a' in 'Name', no longer are visible. Since the letter 'a' is quite common in most languages and names, all records might still be visible but you can try other letters to make the filter function more clear.

As mentioned earlier there is a button on the panel that says 'F'. This 'F' indicates if the filter is on or off. Finally when you're done testing, turn the filter off so that all records are visible.

4.9 Queries

Now that we have played with the filter function a bit, we turn to the query feature of MUIbase. Queries can be used to display information from a database matching certain criteria.

Choose 'Queries' from the 'Program' menu to open the query editor. Now a window with some buttons on the top and two larger areas below appear. The string to the upper left is where you enter the name of what you want to call the query you make.

'Run' Compiles and runs the query.

'Print' Prints the result of the query to a file or on your printer.

'Load and Save'

 Lets you load and save each of the queries.

The first large area is where you enter the query. The second large area is where the result is displayed.

Now let's produce a list of all those persons we tried to filter out previously. Type 'Persons with an a in their name' in the string to the upper left. This is the title for this query. In the upper large area, type:

```
SELECT Name FROM Person WHERE (LIKE Name "*a*")
```

Now when you run this query by pressing the 'Run' button it will produce a list of all persons with the letter 'a' in their name. Try changing the letter to see different results.

At this time we can introduce the AND command. Press the list-view button just to the left of the 'Run' button in the query editor. Then choose 'New' and name it 'Persons with both letter a and s in their names'. Then type

```
SELECT Name FROM Person WHERE
(AND (LIKE Name "*a*") (LIKE Name "*s*"))
```

Note that we are still using the LIKE command for choosing records containing the letters 'a' or 's' in their names, but the AND command requires that BOTH LIKE criteria are met. Therefore, only records with BOTH the letters 'a' and 's' in their name are displayed when the query is run.

4.10 Adding a Table with a Memo and a Button Attribute

These were two ways of selecting and displaying the database. Another way of displaying data can be done by a program. In order to display data we can use an attribute type called memo.

Enter the structure editor and press 'New' in the table section. Name the new table 'Control' and set it's number of records to 'Exactly one'. Click and hold down the mouse

button on the new table. Now drag it just a bit above the middle of table ‘Person’ and release the button. In the table section, ‘Control’ should now be on top, followed by ‘Person’ below.

Make sure that table ‘Control’ is selected, then press ‘New’ in the attribute section. Set the type of the new attribute to ‘Memo’ and give it the name ‘Result’. Press ‘Ok’ and then add another attribute to table ‘Control’ by once again pressing ‘New’ in the attribute section. This time, set it’s type to ‘Button’ and name it ‘Pedigree’.

To give the database a better look, click once on ‘Pedigree’ in the display section and push it to the top by pressing the ‘Up’ button once.

4.11 Programming MUIbase to do a Pedigree

Now we have a button that can start a program and a memo to display data in. It’s therefore time to enter the program editor. This is done by choosing ‘Edit’ from the ‘Program’ menu. The editor has three buttons:

‘Compile & Close’

Which does just that. It compiles the program and leaves the program editor.

‘Compile’ Compiles the programs but stays in the program editor.

‘Revert’ Reverts all changes back to the state when you entered the program editor.

As all program functions you write will reside in this one window, we will need to separate them from each other. In MUIbase this is done by the DEFUN command. Everything between the two parenthesis will be part of the function `pedigree` in this example:

```
(DEFUN pedigree ()
  ; This is DEFUN's end parenthesis
)
```

With this in mind we now type in the first function which will produce a family tree of the current person in the database and place the result in attribute ‘Result’. This `pedigree` function is in fact three functions:

- `pedigree` which sets ‘Control.Result’ by calling another function.
- `getpedigree` which collects the pedigree into a nested list.
- `pedigree2memo` which converts this list to the memo.

```
; The program pedigree

(DEFUN pedigree ()
  (SETQ Control.Result (pedigree2memo (getpedigree Person NIL) 0 3))
)

; The program getpedigree

(DEFUN getpedigree (person:Person level:INT)
  (IF (AND person (OR (NULL level) (> level 0)))
      (LIST person.Name
```

```

        (getpedigree person.Father (1- level))
        (getpedigree person.Mother (1- level))
    )
)
)

; The program pedigree2memo

(DEFUN pedigree2memo (pedigree:LIST indent:INT level:INT)
  (IF (> level 0)
    (+
      (pedigree2memo (NTH 1 pedigree) (+ indent 8) (1- level))
      (IF pedigree (SPRINTF "%*s%s\n" indent "" (FIRST pedigree)) "\n")
      (pedigree2memo (NTH 2 pedigree) (+ indent 8) (1- level))
    )
    ""
  )
)
)

```

When typing this program, make sure that all the parenthesis are where they should be. Too many or too few parenthesis is the most common error you get when MUIbase is compiling your program. The error message from MUIbase probably is ‘Syntax Error’ in this case. Press ‘Compile & close’ and the window closes, which means that there weren’t any mistakes during compiling.

Don’t worry too much if you don’t understand all the functions at first. There is a complete chapter (see Chapter 16 [Programming MUIbase], page 74) containing a reference of all functions including their detailed descriptions.

Now we have a program to run, but first we have to assign the program function to the ‘Pedigree’ button. This is done by entering the structure editor, selecting ‘Control’ in the table section and double-clicking on the ‘Pedigree’ attribute in the attribute section. Then open the list-view ‘Trigger’. In this list, all your program functions will be listed, currently there should be three functions: `pedigree`, `getpedigree` and `pedigree2memo`. Double-click on `pedigree` as the program function the ‘Pedigree’ button will trigger, then press ‘Ok’ and leave the structure editor.

Now if everything is done correctly, pushing the ‘Pedigree’ button will produce a pedigree of the current person. Try changing person to see some different pedigrees.

4.12 Programming MUIbase to List a Person’s Children

As the next addition to this database requires some more records, you should add your brothers and sisters. If you don’t have any then write ‘My faked sister 1’, ‘My faked brother 1’ which of course should be set to have the same parents as you have.

Then go to the program editor and type the following for creating another program.

```

; The program children counts the number of children of a person.
; First we define the variables, e.g. "names" holds the children’s names.

```

```

(DEFUN children ()
  (LET ( (names "") (count 0) (parent Person) )

    ; For all records in table Person do the following:
    ; If the variable parent appears as father or mother
    ; in any of the records then:
    ;   add the name to the variable names
    ;   increase count by 1.

    (FOR ALL Person DO
      (IF (OR (= parent Father) (= parent Mother))
        (
          (SETQ names (+ names Name "\n"))
          (SETQ count (1+ count))
        )
      )
    )

    ; Then we write the result into the Control.Result.
    ; If the current person doesn't have any children, write one string.
    ; If he/she has children then write another string.

    (SETQ Control.Result
      (+ Person.Name (IF (> count 0)
        (+ " is the proud parent of " (STR count) " children.")
        " does not have any children (yet :-).")
      ))
    )

    ; If the parent has children then add their names.

    (IF (<> count 0)
      (SETQ Control.Result
        (+ Control.Result "\n\n"
          (IF (= count 1)
            "The child's name is:"
            "The children's names are:")
          )
        )
      "\n\n"
      names
      )
    )

    ; This is the end parenthesis of the LET-command.
  )

```

```

; This is the end parenthesis of DEFUN children.
)

```

To create variables, we use the **LET** command. Variables created with the **LET** command are local and only visible within the '**LET**' command's open and closing parentheses. Thus any command that accesses these variables has to be placed within these parentheses.

All we need to execute this program is a new program button. Therefore, enter the structure editor and add a button attribute in table '**Control**'. Call it '**Children**' and choose **children** as the program function it should trigger.

To bring some order in the mask of table '**Control**' it's now time to introduce groups. All objects can be ordered into vertically or horizontally aligned groups.

In the display section, click on '**Pedigree**' and shift-click on '**Children**', thereafter you click on the '**Group**' button to the left. Now the two program buttons will be together in a vertically aligned group. However, we want this one to be horizontally aligned so double-click on the '**VGroup**' that has appeared in the display section. This will open a window that lets you change the settings for this group. Set the title to '**Programs**' and check the '**Horizontal**' button.

At this time we can hide the name of attribute '**Result**' in table '**Control**'. Double-click on '**Result**' in the display section and empty the title field. This will display attribute '**Result**' without any title string.

To make things easier, if we add more programs or attributes in table '**Control**', we should place '**Result**' and the '**Programs**' group into a vertical group. Be sure that you have only marked '**Programs**' and '**Result**' then press '**Group**'. This places '**Programs**' and '**Result**' into a vertical group.

Leave the structure editor and take a look at the result. Then press the '**Children**' button to see the number of children and their names of the current person.

This example could very well be extended into a fully-grown pedigree program. The only real limits are your fantasy and the size of your hard drive.

5 Basic Concepts

Before you start setting up your own database projects and entering data for them, you should now about some basic concepts MUIbase is built on.

5.1 Projects

A MUIbase project consists of all relevant information you need for managing your data. This includes the project's user interface, the project's data you entered and the programs you wrote for the project.

A project can be loaded from, saved to, and deleted from disk. Any change you make to a project is only done in memory. At any time you can go back to the state of the last saved project by reloading it.

MUIbase is able to handle multiple projects at a time. Therefore it is not necessary to start MUIbase twice just to load another project.

Furthermore, multiple instances of MUIbase can access the same project. Multiple instances can read the project but only one is allowed to make changes. This should also work across different computers on a network when the project is located on a mounted network drive.

5.2 Tables

MUIbase manages data in tables. A table is organized in rows and columns, where rows are called records and columns are called attributes.

See the following table for an example on how to structure a set of addresses in a table.

Name	Street	City
Steffen Gutmann	Wiesentalstr. 30	73312 Geislingen/Eybach
Charles Saltzman	University of Iowa	Iowa City 52242
Nicola Müller	21W. 59th Street	Westmont, Illinois 60559

There exists a special table kind which can hold exactly one record. A table of this kind is sometimes useful for controlling the database project, e.g. you can put buttons into this table for executing various actions, or a read-only attribute for displaying project related information. For an example suppose you have an account database where you store all your income and expense. An exactly-one table now could have a read-only attribute of type real for displaying the total balance.

Each table has two record pointers, a pointer to the record that is currently displayed in the user interface (called *GUI record pointer*) and a pointer to the record that is the current one while executing a MUIbase program (called *program record pointer*).

You can define any number of tables for a MUIbase project. Tables can be added to, renamed, and deleted from a project.

5.3 Records

A record is one row of a table. It holds all information about one set, e.g. in a table that manages addresses, one record holds one address.

Each record has a record number that reflects the record's position in the table. This number may change when you add or delete records.

For each table a record called *initial record* exists that holds the default values for initializing new records. The initial record always has a record number of 0.

Records can be added to, changed, and deleted from a table. The records are not necessarily held in memory but are loaded from and stored to disk when needed. There are two restrictions for the total number of records of one table. The record number is a 32bit integer value, which (theoretically) limits the total number of records to 4294967295. Another (and more severe) limitation is that for each record a small record header is kept in memory. These limitations still make MUIbase usable for record numbers of 10,000 and more.

5.4 Attributes

An attribute defines one column of a table. It specifies the type and appearance of the corresponding column.

Attributes can be added to, renamed, and deleted from a table. There is no upper limit on the number of attributes per table.

For each attribute you have to specify a type that restricts the contents of this attribute. See the next section for a list of available attribute types.

5.5 Attribute Types

Attributes can be of type string, integer, real, Boolean, choice, date, time, memo, reference, virtual, or button. The types are described in more detail below.

Some of the attribute types support a special value called NIL. This special value has the meaning of an undefined value, e.g. for a type of date it means an unknown date. The NIL value is similar to the NULL value in other database systems.

Please note that once you have set the type of an attribute, you cannot change it later.

5.5.1 String Attributes

String attributes can store any single line of text. Strings are the most often used attribute type in a database project. For example an address database could store the name, street, and city of a person each in its own string attribute.

For a string attribute you have to specify the maximum number of characters allowed in the string. This number does not directly affect the amount of memory or disk space that is used by this attribute because only the actual string contents are stored (other databases have called this feature compressed strings). If necessary the number can be changed after you have installed a string attribute.

String attributes can also be used to store font- and filenames. For filenames external viewers can be launched to display the file contents. Furthermore an in-line image class allows displaying the image of a file.

String attributes do not support the NIL value.

5.5.2 Integer Attributes

Integer attributes store integral values in the range of -2147483648 to 2147483647. They are mostly used for storing quantities of any kind, e.g. the number of children of a person, or the number of song titles on a CD.

Integer attributes support the NIL value representing an undefined integer value.

5.5.3 Real Attributes

Real attributes store floating point values in the range of -3.59e308 to +3.59e308. They are used for storing numbers of any kind, e.g. the amount of money in an income/expense project.

For each real attribute you can specify the number of decimal places used for displaying the real value, though internally always the full precision is stored.

Real attributes support the NIL value representing an undefined real value.

5.5.4 Boolean Attributes

Boolean attributes store one bit of information. They are used for storing yes/no or true/false values, e.g. in a project managing invoices a Boolean attribute could store the 'has paid?' information.

Boolean attributes use TRUE and NIL as Boolean values. NIL in this case stands for a value of FALSE.

5.5.5 Choice Attributes

Choice attributes store one item out of an enumeration of items. For example, in an address project a choice attribute may be used for storing a country name, where the country is one out of 'USA', 'Canada', 'Germany', or 'others'.

A choice attribute does not store the item string but the item number (index) in a record. The number of items and the items itself can be modified after the attribute has been created. However when making changes to a choice attribute, values in existing records are not changed to reflect the new labeling.

Choice attributes do not support the NIL value.

5.5.6 Date Attributes

Date attributes store calendar dates. For example, a date attribute can be used for storing birthdays.

The format for entering and displaying date values can be one of 'DD.MM.YYYY', 'MM/DD/YYYY', or 'YYYY-MM-DD', where 'DD', 'MM' and 'YYYY' are standing for two and four digit values representing the day, month and year of the date respectively.

Date attributes support the NIL value representing an undefined date.

5.5.7 Time Attributes

Time attributes store the time of day or a period of time. For example, a time attribute can be used for storing the durations of music titles on a CD.

The format for entering and displaying time values can be one of 'HH:MM:SS', 'MM:SS' or 'HH:MM', where 'HH' represents the hours, 'MM' the minutes, and 'SS' the seconds. Internally

time values are stored as the number of seconds since 0 AM. Time values larger than 23:59:59 up to the maximum value of 596523:14:07 are possible but negative values are not supported.

Time attributes support the NIL value representing an undefined time.

5.5.8 Memo Attributes

Memo attributes store multi-line text of any size. Text size is handled dynamically which means that memory is only allocated for the actual text size. In a project managing movies for example, a memo attribute can be used to store summaries of the movies.

Memo attributes do not support the NIL value.

5.5.9 Reference Attributes

Reference attributes are a special type of attribute, normally not found in other database systems. Reference attributes store a pointer to another record. The referenced record may reside in the same or in any other table the reference attribute belongs to.

For example in a pedigree project two reference attributes can be used for storing pointers to the father and mother record. Or in a project managing CDs and music titles, a reference attribute in the table holding the music titles can be used to point to the records of the corresponding CDs.

For displaying a reference attribute, any attributes of the referenced record can be specified. Entering a reference attribute can be done by selecting a record from a list of records.

Reference attributes support the NIL value. Here a value of NIL stands for a pointer to the initial record of the referenced table.

5.5.10 Virtual Attributes

Virtual attributes do not store any information in the database itself, but compute them on the fly when needed.

For example, in a project managing invoices where a real attribute holds the amount of money excluding tax, a virtual attribute can be used to "store" the amount of money with tax. Every time the value of the virtual attribute is needed, e.g. for displaying it, it is computed from the corresponding value without tax.

For displaying virtual attributes three kinds exist: Boolean, string and list. These three kinds allow showing the value of the virtual attribute as a TRUE/FALSE value, as a single line of text including numbers, dates, and times, or as a list of several single lines, e.g. for listing all music titles of a CD.

Virtual attributes support the NIL value standing for FALSE (Boolean kind), undefined (string kind), or empty (list kind).

5.5.11 Buttons

Actually, buttons are not a real attribute type as they cannot store or display any information. Buttons are just used for triggering MUIbase programs.

5.6 Table of Attribute Types

The following table summarizes all available attributes types:

Type	Description	Nil allowed?
String	For strings of lengths 1..999. A string can also be used for storing filenames, font-names or one-string-out-of-n-strings. For filenames you can add a field where the contents of the file are displayed as an image.	No
Integer	For storing integer values.	Yes
Real	For floating point numbers.	Yes
Boolean	TRUE or NIL.	Yes (NIL = FALSE)
Choice	One number out of n numbers. Numbers are represented by label strings.	No
Date	For storing a date value (1.1.0000 - 31.12.9999).	Yes
Time	For storing time values (00:00:00 - 596523:14:07)	Yes
Memo	Multi-line text of unlimited length.	No
Reference	For storing a reference to a record of another table.	Yes (NIL means initial record)
Virtual	For displaying results from a MUIbase program.	Yes
Button	For triggering a program function	No (N/A)

5.7 Memory Consumption

Each attribute type needs a certain amount of memory for storing one value in a record. All types except virtual and button have in common that they need a 2 bytes header holding internal information. Additionally, type dependent space is needed for storing the actual value. The following table lists how much memory including a possible 2 byte header one value of the given type needs in memory and on disk.

Type	Memory space	Disk space
String	$2 + 4 + \textit{string-length} + 1$	$2 + \textit{string-length} + 1$
Integer	$2 + 4$	$2 + 4$
Real	$2 + 8$	$2 + 8$
Boolean	$2 + 0$	$2 + 0$
Choice	$2 + 2$	$2 + 2$
Date	$2 + 4$	$2 + 4$
Time	$2 + 4$	$2 + 4$
Memo	$2 + 4 + \textit{memo-length} + 1$	$2 + \textit{memo-length} + 1$
Reference	$2 + 4$	$2 + 4$
Virtual	0	0
Buttons	0	0

Here *string-length* stands for the length of the string to be stored and *memo-length* for the text size of the memo to be stored.

5.8 Relationships

Up to now you know how to organize your information into tables with records and attributes. But you may also want to setup relationships between tables.

For example if you want to collect CDs in a database project you would have two tables, one for the CDs themselves and one for the music titles of the CDs. Of course you could also have all music titles within the CD table but then you would have a fixed number of music titles for each CD.

So having these two tables, you now need a link for each music title to the CD containing this title. This is called a *relationship* between the two tables. In MUIbase you use a reference attribute for setting up such a relationship.

By installing a reference attribute into a table you automatically have a relationship between the table the attribute resides in and the table it refers to.

5.8.1 One to one Relationships

One to one relationships are very simple relationships where for each record you have one or zero partners in another or in the same table.

For example in a database project that manages your favorite movie actors you could setup a reference attribute called ‘**married with**’ that shows the person the actor is married with. An actor that is currently not married does have a NIL value for this reference field.

Of course, no one prevents the user to set the ‘**married with**’ references of several actors all to the same person. However by programming MUIbase it is possible to detect such cases and handle accordingly.

5.8.2 One to many Relationships

One to many relationships are useful for connecting a set of records to one record in another or the same table.

For example in a project managing your bank accounts you could have one table for all bank accounts and one table for all transactions. Now you surely want to know which transaction belongs to which account so you setup a reference attribute in the transaction table referring to the account table.

One to many relationships are the most often used ones. You can use them for managing any hierarchical-like structures, e.g. CDs with music titles, bank accounts with transactions, family trees, etc.

One to many relationships are also the basis for realizing many to many relationships as described in the next section.

5.8.3 Many to many Relationships

Many to many relationships are used when you want a set of records to refer to another set of records.

For example in a project that manages movies and actors you would have two tables, one for the movies and the other one for the actors. Now for each movie you want to know the actors that took part in the movie. So you might think to setup a reference attribute in the actor table that refers to the movie table. But when doing this you could only have one movie referenced for each actor because there is only one reference field in the actor table. So what you need is an unlimited number of references from the actor table to the movie table.

This is done by adding a new table that just has two reference attributes, one pointing to the actor table and the other to the movie table. Now you can enter the relationships by adding new records to this table. For each movie-actor constellation you add a new record and specify the movie and actor by setting the corresponding reference fields.

If you want to know in which movies an actor took part then you only have to search for all records in the new table that refer to the actor in question and look at the movie records the found records refer to. Such a search can be done automatically by MUIbase and the result can be displayed in a list-view.

The following tables show an example of how to connect a set of actors to a set of movies.

	Title	Country
m1:	Batman	USA
m2:	Batman Returns	USA
m3:	Speechless	USA
m4:	Tequila Sunrise	USA
m5:	Mad Max	Australia
m6:	Braveheart	USA

	Name
a1:	Michael Keaton
a2:	Jack Nicholson

```

a3:  Kim Basinger
a4:  Danny DeVito
a5:  Michelle Pfeiffer
a6:  Geena Davis
a7:  Christopher Reeve
a8:  Mel Gibson
a9:  Kurt Russell
a10: Sophie Marceau
a11: Patrick McGoohan
a12: Catherine McCormack
a13: Christopher Walken

```

MovieRef	ActorRef

m1	a1
m1	a2
m1	a3
m2	a1
m2	a4
m2	a5
m2	a13
m3	a1
m3	a6
m3	a7
m4	a8
m4	a5
m4	a9
m5	a8
m6	a8
m6	a10
m6	a11

From these tables you can find out for example that Mel Gibson took part in the movies Tequila Sunrise, Mad Max, and Braveheart, or that in movie Batman the actors Michael Keaton, Jack Nicholson, and Kim Basinger took part.

5.9 User Interface

MUIbase uses a graphical user interface (GUI) organized in a hierarchical way for displaying record contents and for entering data. Each project owns its own main window in which further GUI elements (including sub windows) can be placed. The GUI elements are also called *display objects*.

A table is displayed in an own GUI element called *mask*. A mask can display only one record at a time. Its layout and the attributes included in the mask are customizable by the user.

The following sections describe MUIbase' GUI elements for designing a project's layout.

5.9.1 Windows

Windows can be used to spread information of a project across several independent areas.

Each project automatically has its own main window. If needed, e.g. if the space of the main window exceeds, additional sub windows can be created. Sub windows can also have further sub windows.

For each sub window a window button can be placed into the parent window allowing to open the sub window. The window button looks like a normal text button but may show a small icon to distinguish itself from other buttons.

Main windows do not have a parent window and therefore have no window button. Closing a main window means closing the whole project.

A window can have other GUI elements as children. If no child has been added to a window then a default image is shown.

5.9.2 Masks

A mask is used to display the contents of a table. Only one record of the table can be shown at a time.

The mask may include a panel (see next section) for controlling the table. Other GUI elements like attribute or text objects can be placed into a mask to show the record contents.

Masks cannot be placed inside other masks as this would lead to a hierarchy of masks and therefore to a hierarchy of tables. To setup a hierarchy of tables, use an 1:n relationship between the two tables.

5.9.3 Panels

A panel is a small and wide rectangular area placed at the top edge of a mask. A panel can display a title, e.g. the name of the corresponding table, a pair of numbers showing the record number of the current record and the total number of records, and several buttons for controlling the table, e.g. for displaying the next or previous record.

A panel is part of the table mask but can be hidden if desired. If you setup a panel for a mask then an additional border is drawn around the mask.

5.9.4 Attribute Objects

Attribute objects are used to display the contents of one item of a record.

Depending on the type of the attribute the GUI element is either a string field (types string, integer, real, date and time), a check-mark button (type Boolean), a cycle button or a set of radio buttons (type choice), an editor field (type memo), a pop-up list-view (type reference), a text, check-mark, or list-view field (type virtual) or a text or image button (type button). In some cases the GUI element may also be a simple text field if the attribute object is set to read-only.

5.9.5 Text Objects

Text objects are used for describing the various field elements of a record mask or just to display some static text.

5.9.6 Images

Images can be displayed anywhere in a window. An image can be a pattern, a simple color field, or a pictures in an external file. The image size can be resize-able or fixed.

The image is static. For storing images in a table you use a string attribute (see Section 5.5.1 [String type], page 19).

5.9.7 Space Objects

Space objects are used to insert space in the layout of a window or a table mask. A space object can have a vertical (or horizontal) bar for delimiting other GUI elements.

5.9.8 Groups

GUI elements can be grouped into horizontal or vertical groups. A group places its children from left to right (horizontal group) or from top to bottom (vertical group).

A group can surround its child objects with a rectangular frame, can display an optional title at the top of the group, and can insert space between its child objects.

5.9.9 Balance Objects

Balance objects can be placed between other child objects of a window, mask, or group object. A balance object allows the user to control the weight values of the other child objects and therefore how much space each child gets.

5.9.10 Register Groups

A register group can be used to layout GUI elements into several pages where only one page is visible at a time. This is useful if the user interface becomes too large and you don't want to spread it over several windows.

6 Managing Projects

In this chapter you find how MUIbase organizes projects, how to open, save, delete, and close them, how to check the data integrity and how swapping of records works.

6.1 File Format

A MUIbase project consists of several files stored in a directory owned by the project. This directory is first created when you save the project. Do not make any assumption about the directory structure or filenames inside the directory. In particular, do not remove or place any files or further directories in this directory! They will get lost when reorganizing the project.

The directory contains a file called **Structure.mb** where the descriptions of all tables, attributes, filters, etc. are stored. The record headers are also placed here. For each table you will find a file with the table's name. Here all records of a table are stored. Last but not least there may be several files named **.lock**, **.plock** and **.rlock**. These are used for managing access to the project. Several MUIbase instances may open the project for reading, and acquire a shared access to the **.lock** file. But only one instance is allowed to make changes by acquiring the **.rlock** file, and storing the changes back to disk by acquiring the **.plock** file. Note that for the locking mechanism to work, the file system needs to meet certain guarantees. It is best practice to first test the sharing of a project between different MUIbase instances on a particular file system before relying on this feature.

6.2 Info

MUIbase keeps some information about each project. Select menu item 'Project - Info' to get information about the current project. The information you get consists of the project's name, the number of tables, the total number of records in all tables, and a value that shows how many bytes a reorganization of this project would gain. The gain is however only a rough estimate and should not be treated as an exact number. Especially if you have made many changes to the structure of the project (adding or removing attributes) then this value is far from accurate.

6.3 New Project

MUIbase can handle any number of projects at a time. You are only limited by the available memory. In order to start another project, choose menu item 'Project - New'. This opens a new window with an empty project. You can now define the structure of this project (see Chapter 15 [Structure editor], page 59) or load an existing project from disk (see Section 6.5 [Open project], page 29).

6.4 Clear Project

To reset a project select menu item 'Project - Clear - Project'. This closes the current project and replaces it by an empty project. After starting MUIbase without projects you arrive in this state automatically.

By selecting menu item ‘**Project - Clear - Records**’ you start a new project using the structure of the current one. This means that all except the record data of the current project is used for the new project.

If the current project at the time you selected one of above menu items has not been saved to disk then a dialog appears asking for confirmation of the operation.

6.5 Open Project

To load a project select menu item ‘**Project - Open - Project**’. This opens a file dialog where you can choose a project from. There are also several demo projects that illustrate the capabilities of MUIbase. To load one of them, select menu item ‘**Project - Open - Demo**’.

If the loaded project has its program source set to external, the external source file is created after opening the project (see Section 16.2 [External program source], page 74).

If you were editing a project at the time of choosing any of the above menu items and the project has not been saved then a dialog appears asking for confirmation.

You can also reload a new version of the current project from disk by choosing menu item ‘**Project - Reload**’.

6.6 Save Project

All changes you make to a project are only done in memory or stored temporarily when swapping records (see Section 6.9 [Swap records], page 30). Thus if you want to make them permanent you have to save the project to disk. This is done by choosing menu item ‘**Project - Save**’. If your project doesn’t have a name yet then a file dialog asking for a filename appears first.

The reason why MUIbase does not automatically save a project when it is changed, is that, this way, it is you who decides when to save a project! You can always go back to the last saved version of your project by choosing menu item ‘**Project - Revert to saved**’. This mechanism is similar to the ‘**COMMIT**’ and ‘**ROLLBACK**’ commands in SQL database systems.

If you save a project, all modified records are written to disk and the file **Structure.mb** is recreated. Before creating the new **Structure.mb** file, MUIbase first renames a possibly existing **Structure.mb** file to ‘**Structure.old**’ to have a safety copy in case the save operation fails.

This mechanism guarantees fast load & save operations but it is not free of reorganization. If you have modified many records then the physical place where the records lie and the resulting fragmentation may become disadvantageous. Therefore a menu item ‘**Project - Save & reorg**’ exists that does a save & reorganize operation. This operation may take some time depending on the number and size of the records. The save & reorganize operation creates a new directory and rewrites all project related files. The old directory is deleted on success.

Another good time to schedule a reorganization is when you have done changes to the data-structure of a project, e.g. after you have installed a new attribute in a table. These changes are not applied immediately to all records because it would take too much time to load each record, modify it, and save it back to disk. Therefore these changes are put

on an internal ‘todo’ list which is applied after loading a record. Applying this list to a record takes only little time. However the longer the list gets the more time it needs. Reorganizing a project causes the ‘todo’ list to be applied to all records, so if you have made many changes to the project structure then reorganizing a project will shorten the time for loading records.

You can also save & reorganize a project to a new filename keeping the old project untouched. To do this select menu item ‘Project - Save & reorg as’ which prompts you to enter a new name for the project.

6.7 Admin and User Mode

MUIbase operates either in admin mode (default) or in user mode. You can change between these modes by choosing menu item ‘Project - Change to admin mode’ and ‘Project - Change to user mode’. When in user mode, several menu items are disabled and structure, program and query editor are not available. Therefore, only basic record editing is possible. In admin mode all operations are permitted.

An admin password can be set for a project by selecting menu item ‘Project - Change admin password’. Once set, the password has to be entered when changing into admin mode, or permission is denied leaving the project in user mode.

When opening a project that has an admin password set, the project is started in user mode, otherwise (no admin password has been set), it is started in admin mode.

6.8 Check Data Integrity

MUIbase can verify if all data in your project is still valid and not corrupted by programs trashing your project files or by system crashes. Choose menu item ‘Project - Check data integrity’ for starting this process.

Usually you should never need this functionality and MUIbase should always report that data integrity is perfect. But if it ever happens to you that your project contains ‘**internal errors**’, that is, some records can’t be loaded anymore, then you can repair your project by using this menu item.

MUIbase will write a log file of all affected records and you can save and reorganize the project afterwards. In the log file, records that might be corrupted and records that are not accessible anymore and therefore have been deleted are listed by their record number in the old (corrupted) project and by their record number (in parenthesis) in the reorganized project.

6.9 Swap Records

MUIbase doesn’t need to keep all records of a project in memory. Thus loading and saving of projects is much faster. When loading a project, a record header is allocated for each record. The data itself is only loaded when needed, e.g. when it is displayed on the screen. The total number of records is still limited by available memory since each record header needs some few bytes of memory.

You can specify how much memory MUIbase should use for the records of a project. Choose one of the predefined values found in menu item ‘Preferences - Record memory’ (see Section 7.2.1 [Record memory], page 34). MUIbase does not preallocate a block of

the specified memory size, it only checks from time to time if the current size of allocated memory is larger than the specified value.

If MUIbase runs out of memory or if the upper limit for the record memory size has been reached then MUIbase tries to free as much record memory as possible. In this case MUIbase may write modified records to disk to get the maximum available memory possible. You can also force MUIbase to do this by choosing menu item **‘Project - Swap records’**.

MUIbase maintains a free list for each record file. If you delete a record then the record's file space is added to the free list. Also if you change a record and the record needs to be written to disk then the old file space is added to the free list. However MUIbase makes sure that by reloading you can always go back to the point of the last save operation. MUIbase will not write into areas which are free but where a record still exists that could be reached by reopening the project.

6.10 Close Project

When you are done editing a project you can close it by selecting menu item **‘Project - Close’**. This frees the memory and all resources belonging to the project. If the project contains changes that have not been saved yet then a dialog appears first offering to save, continue or cancel the operation.

For closing a project you can also select menu item **‘Project - Save & close’** which saves the project first if there were any changes and then closes it.

7 Preferences

MUIbase offers several preferences items the user can set to his likes. This chapter shows what preferences items are available and gives general information about how the preferences system works.

All preferences items can be divided into user settings and project settings.

7.1 User Settings

The user settings contain preferences items that depend on the choice of a user, e.g. the user's language, country or taste. The user settings are shown and can be customized in the top part of menu 'Preferences'.

User settings are stored in the environment of the user. On Windows, Mac OS and Linux they are kept in the home directory of the user as `.MUIbase.prefs`. On the Amiga they are stored under `ENV:MUIbase.prefs` and `ENVARC:MUIbase.prefs`.

The user settings contain the preferences items listed below. Whenever any of these items is changed in the 'Preferences' menu, the settings are written to disk in order to make them permanent.

7.1.1 Formats

By selecting menu item 'Preferences - Formats' you can specify the formats used when displaying or printing real and date values. After selecting the menu item a new window appears containing the following items:

- a field 'Real format' for setting the decimal character of real values. You can choose between 'Decimal point' and 'Decimal comma'.
- a field 'Date format' for specifying how date values are output. You can choose between 'Day.Month.Year', 'Month/Day/Year' and 'Year-Month-Day'.
- two buttons 'Ok' and 'Cancel' for leaving the window.

The initial values for real and date formats are determined according to the information found in the operating system's 'locale' environment.

When you are done with all settings, press the 'Ok' button to leave the window and update the display.

7.1.2 External Editor

Besides providing an internal editor built into MUIbase through the employed GUI toolkit, MUIbase also offers to edit text contents by using an external editor (e.g. the context menu of the built-in editor includes an item that allows to call the external editor for editing the contents). The name of the editor and its parameters are specified by selecting menu item 'Preferences - External editor'. You should enter a command string that gets executed when calling the external editor. The special string '%f' can be used at the place of the filename and is replaced with the actual filename (or a temporary filename MUIbase creates for exchanging the text data) before execution.

For example, on Linux you can specify 'emacs %f' for using the powerful GNU Emacs editor, or on the Amiga, you can use 'CED %f -keepio' for switching to the famous CED editor as external editor.

Default is ‘Notepad %f’ on Windows, ‘open -tWn %f’ on Mac OS, ‘gvim -f %f’ on Linux, and ‘Ed %f’ on the Amiga.

Note that on Mac OS, the default setting starts the external editor synchronously, i.e. MUIbase waits for the editor to quit (see the ‘-W’ and ‘-n’ flags in ‘open --help’). This is required when using menu item ‘External editor’ in the context menu of a Memo attribute (see Section 9.3 [Changing records], page 40) and when using the EDIT command for programming MUIbase (see Section 16.23.1 [EDIT], page 137).

On the Amiga, additionally the sequence ‘%p’ can be used in the command string. When calling the external editor this sequence is replaced by the name of the public screen MUIbase is running on.

7.1.3 External Viewer

MUIbase uses an external viewer for displaying the contents of external files, e.g. images, movies or any kind of documents. For example you can use the string data type for storing filenames in a table and then let MUIbase display them using the external viewer. To specify this viewer select menu item ‘Preferences - External viewer’. Like for the external editor (see Section 7.1.2 [External editor], page 32) you have to enter a command string here.

Default is ‘%f’ on Windows (using ShellExecute), ‘open %f’ on Mac OS, ‘gnome-open %f’ on Linux, ‘Open %f’ on MorphOS, and ‘Multiview %f’ on other Amiga systems.

Note that on Mac OS, the default setting always starts the external viewer asynchronously, i.e. MUIbase never waits for the viewer to quit. If you are running Mac OS 10.5 or higher then you can use ‘open -Wn %f’ for enabling synchronous viewing. This is required when using the VIEW command for programming MUIbase (see Section 16.23.3 [VIEW], page 137).

On the Amiga, additionally the sequence ‘%p’ can be used in the command string. When calling the external viewer this sequence is replaced by the name of the public screen MUIbase is running on.

Starting with MUIbase 4.0 an external viewer is chosen automatically based on your system settings on Windows and Linux, and this setting is not available.

7.1.4 Extra Buttons in Tab Chain

In the graphical user interface specified in the structured editor there might exist several extra buttons. Under extra buttons fall popup buttons, e.g. file, font or listview popups beneath a string field, auto-show and filter buttons of a reference field, and view buttons next to a string field.

These buttons are usually not included in the cycle chain, that is, you can’t use the *Tab* key to activate them. However if you check menu item ‘Preferences - Extra buttons in Tab chain’ then these buttons are also included in the Tab chain. Default is checked.

On the Amiga please note that changing the status of this menu item has only an effect after rebuilding the user interface, e.g. by switching to the structure editor and back to the user interface.

7.1.5 Advance on Enter

When the cursor is in an editable single-line text field in the user interface of a project, pressing the *Enter* key can either advance to the next item in the user interface or keep the cursor in the current text field.

If you check menu item ‘**Preferences - Advance on <Enter>**’ then the cursor jumps to the next item in the user interface, otherwise it stays on the current text field. Default is checked.

Note that in any case, pressing *Enter* confirms and stores the entered text.

7.1.6 Confirm Quit

If you try to quit MUIbase and there are unsaved projects then a dialog pops up asking for confirmation. However if all projects have been saved, MUIbase quits silently.

In order to always enforce confirmation when quitting MUIbase, menu item ‘**Preferences - Confirm quit**’ has to be checked. In this case you always get a confirmation dialog when selecting menu item ‘**Project - Quit**’ or when closing the last open project. Default is unchecked.

7.1.7 MUI

Amiga only. As MUIbase on the Amiga is a MUI application, you can also specify the MUI preferences for this application by choosing menu item ‘**Preferences - MUI**’.

7.2 Project Settings

Project settings consists of preferences items that are stored along with a project. These items are shown and changeable in the lower part of menu ‘**Preferences**’ and in menu ‘**Program**’ (the reason to spread these among two menus is to keep menus compact and clear).

The following preferences items belong to the project settings. Whenever any of these settings is changed, the count of changes for the project is incremented.

7.2.1 Record Memory

MUIbase does not need to keep all records of a project in memory. Instead it uses a buffer for holding only a small number of records. By choosing a value from menu item ‘**Preferences - Record memory**’ you can set the size of this buffer. Each project has its own buffer, so if you have opened two projects each having a record buffer size of 1MB, MUIbase will use up to 2MB for the records of both projects.

MUIbase does not allocate the memory a priori but uses a dynamic allocation scheme. Furthermore, the specified buffer size is only a soft limit and occasionally MUIbase might exceed it.

Once the buffer gets full, or if MUIbase runs out of memory, all records are flushed from the buffer. This means that unchanged records are simply freed and changed records are first written to disk and then freed (see Section 6.9 [Swap records], page 30).

By giving MUIbase a higher value for the record buffer you can notice a speed increase in accessing the records as more records can be held in memory and fewer disk access is

needed. If there is enough memory to hold all records in memory and if you have specified a large enough memory limit (e.g. ‘unlimited’) then MUIbase operates with optimal speed.

Default is ‘unlimited’.

7.2.2 Confirm Delete Record

You should check menu item ‘**Preferences - Confirm delete record**’ if you want MUIbase to pop up a dialog asking for confirmation whenever you try to delete a record. Leave the item unchecked if records should be deleted silently. Default is checked.

7.2.3 Paths Relative to Project

If you want to reference external data (e.g. documents or images) then the filename of these data need to be stored in the project. For this purpose you can use absolute path names or path names containing assign names (see Section 3.8 [Filename conventions], page 7). Another way is to store external data relative to the directory of the project (note: this is not the project directory itself but the directory containing the project).

By activating menu item ‘**Preferences - Paths relative to directory of project**’, MUIbase changes the current working directory to the directory containing the project. This means that if you have several projects open, MUIbase changes directories according to the currently active project. Once this menu item has been activated for a project, filenames can be specified relative to the directory of the project. This makes a project independent of where it is stored in the file system.

If you leave this menu item unchecked, MUIbase uses the initial working directory when the program was started.

Default is unchecked.

7.2.4 Confirm Auto Reload

When MUIbase finds an updated version of your project on disk, it automatically reloads the project. If menu item ‘**Preferences - Confirm auto reload**’ is checked, MUIbase first opens a dialog for confirming the reload operation. If unchecked, the project is reloaded silently. Default is checked.

7.2.5 Confirm Save & Reorg

Saving and reorganizing a project can take quite some time depending on the size of the project. Therefore, if you select menu item ‘**Project - Save & reorg**’ or ‘**Project - Save & reorg as**’, a dialog pops up asking for confirmation of this operation. The dialog only appears if menu item ‘**Preferences - Confirm save & reorg**’ is checked, thus you can disable this dialog by de-selecting the menu item. Default is checked.

7.2.6 Program Source

You can set the program source of a project in menu item ‘**Program - Source**’ to be ‘**Internal**’ or ‘**External**’. If set to ‘**Internal**’, you can use MUIbase’ built-in editor for editing and compiling the project’s program. This is the default. If you wish to use an external editor for programming, you choose ‘**External**’ and enter the name of a new file to which MUIbase then writes the program source. This allows to load and edit the program source into your favorite editor. For more information about how to use this feature, see Section 16.2 [External program source], page 74.

Note that when setting this menu item from ‘**External**’ back to ‘**Internal**’, the last successfully compiled version of the program is kept.

7.2.7 Cleanup External Program Source

Menu item ‘**Program - Cleanup external program source**’ decides if the external program source file of a project should be deleted when closing the project or when changing menu item ‘**Program - Source**’ back to ‘**Internal**’. See Section 16.2 [External program source], page 74, for more information about external source files. Default is checked.

7.2.8 Program Debug Information

For compiling a project’s program, you can choose whether debug information should be included in the executable or not. If you compile without debug information and a runtime error occurs then an error description is generated but there is no information about where exactly the error occurred. If you compile with debug information then you also get the exact error location. Compiling with debug information is a bit slower, requires more memory and the resulting program is slightly less efficient.

Use menu item ‘**Program - Embed debug information**’ to turn debug information for compilation on and off. Default is checked. After changing this state, don’t forget to recompile the project’s program by choosing menu item ‘**Program - Compile**’.

7.2.9 Obsolete Functions

Since MUIbase version 2.7 a few programming functions have been made obsolete (see Section 16.30 [List of obsolete functions], page 151). The functionality of these obsolete functions have been replaced by other mechanisms and the functions do not work as expected any longer. When opening projects containing programming functions which are now obsolete, you can choose how to handle them.

Menu item ‘**Program - Obsolete functions**’ specifies how to react when an obsolete function is called. When choosing ‘**Ignore silently**’ any call of an obsolete function is ignored and program execution continues by skipping over the function call. ‘**Warn when called**’ opens a dialog window informing the user whenever an obsolete function is called and allows to continue execution or to abort with an error message. This is the default. If ‘**Treat as error**’ is selected, any call of an obsolete function generates an error and compilation of programs containing obsolete functions fails with a proper error message.

It is recommended to choose ‘**Treat as error**’ after all calls of obsolete functions have been removed from a project program. In order to find out if your project contains any calls of obsolete functions select ‘**Treat as error**’ and recompile the project program.

7.2.10 Sort Trigger Functions

If menu item ‘**Preferences - Sort trigger functions in pop-ups**’ is checked then functions available as triggers are sorted alphabetically for display in dialogs for creating and changing tables (see Section 15.1.1 [Creating tables], page 59) and for creating and changing attributes (see Section 15.2.1 [Creating attributes], page 61). Otherwise, functions are listed as they occur in the project’s program. Default is unchecked.

7.2.11 Program Include Directory

The programming feature of MUIbase allows to include external source files within the project's program (see Section 16.3.3 [#include], page 75, for more information). Menu item 'Program - Include directory' allows to set a directory where MUIbase should search for such include files. Default is 'MUIbase:Include'.

7.2.12 Program Output File

When executing a MUIbase program all output directed to 'stdout' is actually printed to a file. The name of this file can be entered in a dialog by choosing menu item 'Program - Output file'. You also specify if the output should be appended to the file or if the file should be erased and re-created on new output.

On Windows, Mac OS and Linux you can direct the output to an external program for processing the data. For this, the first character of the filename must be the pipe symbol '|' followed by the external program and its arguments. The external program has to read the data from its standard input. This allows on Linux for example the following re-directions:

- |lpr prints the output on the default printer.
- |mknod /tmp/pipe p; (xterm -e less -f /tmp/pipe &); cat > /tmp/pipe; rm /tmp/pipe displays the output using the program 'less' in its own 'xterm' window.
- /dev/pts/0 writes the output to a terminal connected to 'pts/0'. On some desktop environments, e.g. KDE, a daemon listens to this terminal and the output gets displayed in a window.
- /dev/stdout passes the output to the standard output channel of MUIbase. This is the default.

On the Amiga there are a few special filenames for directing the output, e.g.:

- PRT: prints the output on your printer.
- CON:///MUIbase output/CLOSE/WAIT prints the output in a Shell window.
- CONSOLE: prints the output in the Shell window where MUIbase has been started from. This is the default.

7.3 Save as Default

The project settings are individual for each project, i.e. different projects can have different settings. For new projects a default setting is chosen. This default setting is stored together with the user settings in the user environment (see Section 7.1 [User settings], page 32).

In order to customize the default settings to your needs, you can store the settings of the current project as the default settings for new projects by choosing menu item 'Preferences - Save as default'.

8 Log

This chapter describes the logging facility of MUIbase including the internal ‘_Log’ table, how to activate logging, the setting of a label for new log entries, how to import, export, and clear the log, and how to view all log entries.

8.1 Log Table

For logging changes to a project, MUIbase uses an internal table named ‘_Log’. Note the underscore as the first character which indicates that this table is a system table managed by MUIbase that cannot be changed. The table contains the following attributes which are all of type string:

Name	Description
‘_Label’	a field that can be set by menu item ‘Log - Set log label’ or computed by a trigger function with name logLabel (see Section 8.3 [Set log label], page 39).
‘_Date’	date of log entry.
‘_Time’	time of log entry.
‘_Action’	one of ‘New record’, ‘Delete record’ or ‘Change value’.
‘_Table’	name of the table where action occurred.
‘_Record’	number of the record where action occurred at the time of the action. Note that the record number may change when adding or deleting records, or when re-ordering records of a table.
‘_Description’	description of record where the action occurred. The record description can be specified in the table object (see Section 15.3.2 [Table object editor], page 65).
‘_Attribute’	If the action is ‘Change value’ then this field holds the name of the attribute where the change occurred.
‘_OldValue’	Old value of attribute (for action ‘Change value’).
‘_NewValue’	New value of attribute (for action ‘Change value’).

The ‘_Log’ table can be accessed like any other table of a project. For example, a select-from-where query

```
SELECT * from _Log
```

can be run in the query editor for obtaining a list of all changes (see Section 14.1 [Select-from-where queries], page 53, and Section 14.2 [Query editor], page 53).

8.2 Activate Logging

By default, logging is not enabled in a project. In order to start logging changes, select menu item ‘Log - Logging active’. The state of this menu item is stored in the project file, thus, once activated and saved, changes will be kept logging when re-opening the project. De-activate the menu item to stop logging changes.

Note that only for those tables and attributes, that have the ‘Log changes’ property set, will changes be logged (see Section 15.1.1 [Creating tables], page 59, and Section 15.2.1 [Creating attributes], page 61). The changes that are logged are adding a new record, deleting a record, or changing a field in a record. For each such action, a new log entry is created and added to the ‘_Log’ table.

8.3 Set Log Label

The ‘_Log’ table has an attribute named ‘_Label’ that can be freely set by the project. Choosing menu item ‘Log - Set log label’ opens a dialog for entering the label text.

It is also possible to provide the label through a program function. The function should have the name `logLabel` and is called for each new log entry. The function does not have any arguments and the returned expression, converted to a string, is used as the label text. For more information about this trigger function, see Section 16.29.6 [`logLabel`], page 146.

Note that when the function `logLabel` exists, menu item ‘Log - Set log label’ is disabled.

8.4 Import Log

It is possible to import log entries from an external file. This can be useful when older log entries have been deleted from the log. After selecting menu item ‘Log - Import log’ a window is opened that allows importing records in the ‘_Log’ table. See Section 13.3 [Importing records], page 52, for a description on all import options.

8.5 Export Log

When the ‘_Log’ table becomes large, it can be useful to export older log entries to an external file. To do this, choose menu item ‘Log - Export log’. This opens a window for exporting the records of the ‘_Log’ table to a file. See Section 13.4 [Exporting records], page 52, for a description on all export options.

8.6 Clear Log

For clearing all entries of the log, choose menu item ‘Log - Clear log’. A typical case for clearing all log entries is when the ‘_Log’ table becomes large. Make sure to export all entries to an external file prior to clearing the log.

8.7 View Log

By choosing menu item ‘Log - View log’ the query editor is opened with a pre-defined query that lists all log entries. You can modify the query and its title, and MUIbase will remember the query. For more information, see Section 14.2 [Query editor], page 53.

9 Record-Editing

This chapter describes how to add, change, delete, browse, and view records of a database table.

9.1 Active Object

MUIbase uses a cursor for displaying which object is the active one. If the active object is a string object, the usual text cursor appears, other objects get a special frame around them. You can cycle through the active objects by pressing the *Tab* or *Shift-Tab* keys. If you press the *Help* or *F1* key, an external viewer is loaded with helpful information about the active object.

The table in which the active object resides is called the *active table*. The panel of a table can be set to the active object. This ensures that you can always set a table to be the active one, although the table may not contain any other activate-able objects.

On Windows, Mac OS and Linux each table has a context menu containing menu items for manipulating the table. This context menu can be opened by pressing the right mouse button somewhere inside the table mask (but outside any other GUI object that has its own context menu).

On Mac OS and Amiga the table menu items are part of the global menu found at the top of the screen.

9.2 Adding Records

If you select menu item ‘**Table - New record**’ a new record is allocated in the active table. The record is initialized with the initial values for all attributes. It is also possible to duplicate the current record of the active table by selecting menu item ‘**Table - Duplicate record**’.

If you have installed a trigger function for adding a new record (see Section 15.1.1 [Creating tables], page 59) then this trigger function is called for creating the record. For more information on this mechanism, See Section 16.29.8 [New trigger], page 146.

9.3 Changing Records

To change the current record in a table you can activate any attribute object within the table’s mask and enter a new value. For string, integer, real, date, time, and memo attributes you can use the usual editing commands.

An attribute object may have been configured as read-only. In this case you can’t change its value (exception: string attribute with pop-up button).

9.3.1 String Attributes with Pop-up Button

If a string attribute has a pop-up button attached to it then you can press the pop-up button and get a pop-up to set the string contents, e.g. a file dialog for choosing a filename, or a list of strings to choose one from. The pop-up button can always be used to set the string attribute’s value even if the attribute is set to read-only.

Right to the string field another small button might appear. Pressing this button calls an external viewer to display the file specified in the string field.

9.3.2 Entering Integer Values

When entering an integer number, one can use an octal notation (leading 0) or hexadecimal notation (leading 0x) besides the usual decimal notation.

9.3.3 Entering Boolean Values

The checked state of Boolean attribute can be toggled with the left mouse button, or with the space bar if the object is the active one.

9.3.4 Entering Choice Values

For choice attributes you can choose a value by clicking onto it, or by using the *Up* and *Down* cursor keys to browse through all choice labels.

9.3.5 Entering Date Values

Date values can be entered in one of the formats ‘DD.MM.YYYY’, ‘MM/DD/YYYY’ or ‘YYYY-MM-DD’, where ‘DD’, ‘MM’ and ‘YYYY’ are standing for two and four digit values representing the day, month and year of the date respectively. It is possible to omit the year value of a date. In this case the current year is used.

By inserting a single integer value, a date value relatively to the current date can be specified, e.g. when entering ‘0’ the today’s date is used, or when entering ‘-1’ yesterday’s date is used.

9.3.6 Entering Time Values

The format for entering time values is specified in the structure editor (see Section 15.3.3 [Attribute object editor], page 66). Possible formats are ‘HH:MM:SS’, ‘MM:SS’ or ‘HH:MM’ where ‘HH’ represent the hours, ‘MM’ the minutes, and ‘SS’ the seconds.

It is possible to omit parts of the format, e.g. entering ‘6:30’ under the format ‘HH:MM:SS’ automatically expands to ‘00:06:30’. When entering a single number, it is regarded as the number of seconds (formats ‘HH:MM:SS’ and ‘MM:SS’) or as the number of minutes (format ‘HH:MM’) respectively, and the corresponding time value is computed.

9.3.7 Memo Context Menu

Memo attributes have a context menu that offers further editing possibilities:

- ‘Cut’, ‘Copy’, and ‘Paste’ allow exchanging data with the clipboard.
- ‘Delete’ erases selected text and ‘Select all’ allows to select all text (Windows, Mac OS and Linux).
- ‘Clear’ deletes all text in the memo (Amiga).
- ‘Undo’ and ‘Redo’ allow going back and forth the changes you made to the memo contents (Amiga only).
- ‘Input methods’ and ‘Insert unicode control character’ are GTK-specific menu items (Windows, Mac OS and Linux). Please refer to the GTK documentation.
- With ‘Open text’ and ‘Save text’ you can load and save the memo contents from/into a file.
- ‘External editor’ launches an external editor for editing the memo. See Section 7.1.2 [External editor], page 32, for more information about the external editor.

9.3.8 Select-from-where List Context Menu

Virtual attributes with the ‘List’ kind have a context menu containing the following entries:

- ‘Export as text’ for exporting the list to a text file (see Section 14.3 [Exporting queries as text], page 54).
- ‘Export as PDF’ (most systems) for exporting the list to a PDF file (see Section 14.4 [Exporting queries as PDF], page 55).
- ‘Print’ for printing the list (see Section 14.5 [Printing queries], page 55).

9.3.9 Entering Reference Values

For reference attributes the record reference can be entered through a pop-up list:

- To the right of a reference attribute you find a pop-up button which, if pressed, opens a list of records. Choose a record from the list to set the reference to this record, ‘Initial’ to set the reference to the NIL value, or ‘Current’ to set the reference to the current record of the referenced table.
- You can search for an entry in the referenced table by using the keyboard. After the first key press an input field is opened allowing to enter more characters for the search pattern. After each key press, a search is started immediately (case-insensitive) and the first matching entry is selected. The search method can be specified in the display object of the attribute (see Section 15.3.3 [Attribute object editor], page 66) under the ‘Quick search’ category. You can use the characters ‘*’ for matching an arbitrary sequence of characters and ‘?’ for matching exactly one arbitrary character. Using the cursor keys *Down* and *Up*, the next respectively previous matching entry is selected. A selected entry is stored when acknowledged by pressing the *Enter* key. If you leave the search window by other means, e.g. pressing *Esc*, then the attribute stays unchanged and keeps its previous value.

A reference attribute can also be set by dragging a line from a list of a virtual attribute and dropping it onto the reference field. If the dragged line was generated from a record of the referenced table then this record is used as the new record reference.

9.3.10 Entering NIL Value

To enter the NIL value, enter any invalid string for the given attribute type, e.g. if you enter ‘xyz’ in an integer attribute then the value of this attribute is set to NIL. Please note that not all attribute types support the NIL value. See Section 5.6 [Table of attribute types], page 22, for an overview of all attribute types.

9.4 Deleting Records

To delete the current record chose menu item ‘Table - Delete record’. Before deleting the record a dialog may appear asking you for confirmation. You can enable and disable this dialog in the preferences settings (see Section 7.2.2 [Confirm delete record], page 35).

If you have installed a trigger function for deleting records (see Section 15.1.1 [Creating tables], page 59) then this trigger function is called for deleting the record. For more information on this mechanism, see Section 16.29.9 [Delete trigger], page 147.

It’s also possible to delete all records of a table by choosing menu item ‘Table - Delete all records’. Only records matching the record filter of the corresponding table are

deleted. Before deletion a confirmation dialog appears, if enabled. No trigger function is called when deleting all records.

9.5 Browsing Records

To view other records than the currently displayed one, select one of the sub menu items in menu item ‘Table - Goto record’. You can go to the previous, next, first, or last record, jump several records backward or forward, or enter the record number of the record you want to view. The record number in this context is the number that is displayed in the corresponding panel for that record (see Section 5.9.3 [Panels], page 26). The panel may also include two arrow buttons for going to the previous and next record.

Record browsing can be easily done using the *Up* and *Down* cursor keys in combination with the *Shift*, *Alt*, *Command* and *Ctrl* keys. All possible combinations are listed in menu item ‘Table - Goto record’. On Windows, Linux and Amiga the combinations are:

	<i>Alt</i>	<i>Shift-Ctrl</i>	<i>Shift-Alt</i>
<i>Up</i>	Previous record	First record	Jump backward
<i>Down</i>	Next record	Last record	Jump forward

On Mac OS the combinations are:

	<i>Command</i>	<i>Ctrl-Command</i>	<i>Shift-Command</i>
<i>Up</i>	Previous record	First record	Jump backward
<i>Down</i>	Next record	Last record	Jump forward

9.6 View all Records

It is possible to view all records of a table by choosing menu item ‘Table - View all records’. This opens the query editor with a pre-defined query for listing all records of the current table. You can modify the query and its title, and MUIbase will remember the query. For more information, see Section 14.2 [Query editor], page 53.

10 Filter

Filters can be used to hide records. This chapter describes what types of filters are available and how to use them.

MUIbase knows two types of filters, record filters and reference filters.

10.1 Record Filter

A record filter can be installed into a table to filter out records that are not of interest to you. Records that are filtered out are excluded in the table mask and thus the user can't see or browse to them.

10.1.1 Filter Expression

A filter is defined by specifying a Boolean expression that may contain calls to MUIbase programming functions. For each record of the table the filter is specified for, this expression is evaluated. If it returns NIL then the record is filtered out, otherwise it is included in the table mask.

Each table can have its own filter expression.

10.1.2 Changing Filters

To change the filter of the current table select menu item 'Table - Change filter'. This will open a window containing

- the name of the table you install the filter for in the window title.
- a list of all attributes of the table that can be used in the filter expression. This list is placed in the left part of the window. If you double click a name then the name will be inserted into the filter expression at the current cursor position.
- a table of buttons displaying MUIbase programming functions and operators placed in the right part of the window. Click on one of the buttons to enter the corresponding function in the filter expression. Please note that the presented list of functions and operators is not complete. Other MUIbase functions not shown in one of the buttons must be entered manually. Only those MUIbase functions can be used that don't have side effects, e.g. it is not possible to write data to a file within a filter expression.
- a string input field to enter the filter expression. The attribute and function/operator names are inserted here. You can also directly input your filter expression.
- two buttons 'Ok' and 'Cancel' to leave the window.

After you are done with the specification of the filter expression click on the 'Ok' button to leave the window. The entered expression is now compiled and on successful compilation, the expression is evaluated for all records. Those records for which the Boolean expression doesn't hold are then discarded in the table mask.

In case the expression doesn't compile you will get an error message displayed in the window title bar.

A filter can be turned on and off by clicking on the 'F' button in the table's panel (if it is installed). After you have specified a filter expression for a table the filter for this table is turned on automatically.

If you (re-)activate a filter then all records of the table are checked whether they match the filter or not.

If a filter is currently active and you change a (filter relevant) attribute in a record of this table then the match-filter state of this record is not recomputed and stays unchanged.

If you allocate a new record in a table with an activated filter then there is no check if the new record matches the filter and the new record has its match-filter state set to TRUE.

10.1.3 Filter Examples

Here are some examples for valid filter expressions:

- ‘NIL’ filters out all records.
- ‘TRUE’ doesn’t filter out any record.
- ‘0’ has the same effect as ‘TRUE’ because for MUIbase all expressions not equal to NIL are considered as TRUE.
- ‘(> Amount 100.0)’ only displays records where the ‘Amount’ attribute is greater than 100.0 (we assume here that the table has an attribute ‘Amount’ of type real).
- ‘(NOT (LIKE Name "*x*))’ filters out all records that have the letter ‘x’ in the ‘Name’ attribute (a string attribute).

Please note that MUIbase’ programming language uses a lisp-like syntax. For more information about the programming language, see Chapter 16 [Programming MUIbase], page 74.

10.2 Reference Filter

Reference attributes can also have a filter behavior. This is useful e.g. for building a hierarchy of tables. As an example see the project ‘Albums’.

If the filter of a reference attribute is turned on then the following features are activated:

1. The user can only access records in the attribute’s table that have the reference set to the current record of the referenced table.
2. If the referenced table changes its current record then also a new current record is searched and set for the attribute’s table.
3. When allocating a new record the reference is automatically set to the current record of the referenced table.

Note: Cascading delete has to be implemented manually (by using a delete trigger function).

Do not use the reference filter on cyclic graphs, e.g. self-referencing tables, as it doesn’t make much sense.

11 Order

For each table in your database you can specify in which order its records should be displayed. This chapter describes how you can specify an order and what consequences it has.

11.1 Empty Order

By default each newly created table has an empty order. This means that if you enter a new record, the created record is inserted at the current position, that is, behind the current record of the table. If you change some fields of an existing record, the position of the record within the table stays unchanged.

11.2 Order by Attributes

Sometimes it is useful to have the records sorted by a certain attribute, e.g. by the ‘Name’ attribute if the table has one.

In MUIbase you can specify for each table a list of attributes by which its records should be sorted. All records are first sorted by the first attribute in this list. If two records are equal in an attribute then the next attribute in the list determines the order. For each attribute you can specify if the records should be sorted ascending or descending.

For determining the order of attributes the rules of the following table are used:

Type	Order relation
Integer Choice	NIL < MIN_INT < ... < -1 < 0 < 1 < ... < MAX_INT (Choice values are treated as integers)
Real	NIL < -HUGE_VAL < ... < -1.0 < 0.0 < 1.0 < ... < HUGE_VAL
String Memo	NIL < "" < ... < "a" < "AA" < "b" < ... (String comparison is done case insensitive)
Date	NIL < 1.1.0000 < ... < 31.12.9999
Time	NIL < 00:00:00 < ... < 596523:14:07
Boolean	NIL < TRUE
Reference	NIL < any_record (Records itself are not comparable for ordering)

If you have specified an order for a table then the records are automatically rearranged whenever you add a new record or change an order-relevant field of a record.

11.3 Order by a Function

Sometimes you want a more complex ordering scheme than a simple attribute list as described in the last section. For example, an attribute list can't hold reference attributes, so it is not possible to sort your records by a reference field. The reason for this is that with reference attributes MUIbase is not able to keep your records ordered at all times (see Section 16.29.10 [Comparison function], page 147, in the MUIbase programming chapter for more details).

However, MUIbase also offers the possibility to specify a comparison function for sorting your records. You can specify any function that you have written using the MUIbase program editor. The function will be called with two record pointers and the returned value should reflect the order of the two records. The function can use any operations for comparing the records, thus it can e.g. compare records using reference attributes. For more information on this mechanism, see Section 16.29.10 [Comparison function], page 147.

If you decide to use a comparison function for ordering a table then please note that MUIbase cannot always detect when records of the table have to be reordered since the dependencies are unknown. Use menu item 'Table - Reorder all records' when records are becoming unsorted.

11.4 Changing Orders

To specify an order for the current table select menu item 'Table - Change order'. This will open a window containing

- the name of the table in the window title.
- a choice field 'Type' where you specify whether the table should be ordered by using an 'Attribute list' or by using a 'Comparison function'. Depending on the state of 'Type' you can enter data into the following items.

For an order using an attribute list, the following items exist:

- a list of all attributes of the table that can be used in the order list. This list is placed in the left part of the window. If you double click a name then the name will be inserted into the order list at the current cursor position.
- the current list of attributes used for ordering. This list is placed in the right part of the window. The top item in this list is the first attribute of the order list. You can rearrange items by dragging them to other positions in the list. To add further attributes drag them from the attribute list to the order list. You can remove an attribute from the order list by dragging the item out of the order list and dropping it onto the attribute list.

Each entry in the order list has an arrow symbol pointing up or down on the left side. You can toggle the state of the arrow by double-clicking it. If an arrow is pointing up then the sorting order for this attribute is done ascending, if it is pointing down, it is done descending.

For an order using a comparison function, there is the following item:

- a field 'Function for comparing records' where you can enter the name of a function that should be called for comparing two records of the table. You can use the pop-up button to the right of the string field for choosing a name from a list of all function

names. If you leave the field empty then an empty order is used. For more information on how to use a comparison function, including the arguments that are passed to it, see Section 16.29.10 [Comparison function], page 147.

Furthermore, the following buttons exist:

- a **‘Clear’** button that clears all fields for an empty order.
- two buttons **‘Ok’** and **‘Cancel’** for leaving the window.

To enter a new attribute order list, choose **‘Attribute list’** in the **‘Type’** field and press the **‘Clear’** button. Then use drag & drop as described above to build up a new list of attributes. If you want to have an empty order then just don’t add any attributes to the order list.

When you are done specifying the order, press the **‘Ok’** button. MUIbase will then reorder all records of the table.

11.5 Reorder all Records

If you ever think that some records of a table became unsorted, e.g. when using a comparison function for ordering, then you can choose menu item **‘Table - Reorder all records’** for sorting all records.

12 Search For

For record browsing you can use a search dialog to search for a specific record. The search feature uses a search pattern that you provide and checks all records for a successful match with this pattern. If it finds one then this record will be displayed in the table mask.

12.1 Search Dialog

To open the search dialog select menu item **‘Table - Search for’**. This will open a window containing

- a string field for entering the search pattern. Use the characters **‘*’** and **‘?’** as jokers. The character **‘*’** matches any number of characters (including zero characters) whereas **‘?’** matches exactly one single character.
- a field **‘Case sensitive’**. If you check it, searching uses case sensitive string comparison, otherwise case insensitive string comparison is used.
- a field **‘All fields’**. If checked then all fields of a record are tested for a successful match with the search pattern. Otherwise only the attribute which has been the active one when the search dialog has been opened is tested. In case the active object at the time when opening the search dialog has not been an attribute object, this field is checked and disabled automatically.
- two radio buttons for the search direction, **‘Forward’** and **‘Backward’**.
- two radio buttons for specifying from which record the search should be started. **‘First/last record’** will start the search from the first or last record depending on the search direction. **‘Current record’** starts the search from the current record.
- two buttons **‘Search’** and **‘Cancel’** for leaving the window.

After you have entered a search pattern and left the dialog with the **‘Search’** button MUIbase starts searching for a matching record. The comparison of an attribute field with the search pattern is always done string based, attribute fields of non-string types are therefore converted to strings first.

If a matching record is found, it is displayed as the current record in the table mask. Otherwise a **‘Search pattern not found’** message appears.

If you search on an attribute that is used as the first attribute for ordering and your search pattern doesn’t start with a joker (**‘*’** or **‘?’**) then an improved search algorithm (binary search) is used that makes use of the record order. This can speed up searching significantly.

12.2 Forward/Backward Search

Two further menu items allow to search for the next and the previous occurrence of the search pattern. Select menu item **‘Table - Search forward’** for browsing to the next record that matches the search pattern, and **‘Table - Search backward’** to go to the previous matching record.

12.3 Search Pattern Examples

Here are some search pattern examples:

- ‘Lassie’ searches for records that have the string ‘Lassie’ in one of the search attributes.
- ‘*x*’ searches for records that have the letter ‘x’ in one of the search attributes.
- ‘???’ searches for records that have exactly three characters in one of the search attributes, e.g. a record with an entry ‘UFO’.

13 Import and Export

For sharing your records with other databases, MUIbase offers a way to import and export records from and to other databases. Import and export is done by reading and writing text files. The text files must follow a special format described in the next section.

13.1 File Format

For importing records into MUIbase, all records of a table should be in a single text file. If records of several tables are to be imported, they should be in separate import files, one for each table.

An import file consists of lines and columns. Lines are separated by a record delimiter, columns by a field delimiter. The delimiters can be specified in the import and export dialog. Since a record field itself may contain such a delimiter, double quotes can be used around all fields for escaping delimiters.

The import file should be of the following structure:

- The first line contains the field names. For each name the table where the records are imported to must contain an attribute with the exact same name. In case no matching attribute is found for a given name, the import fails with an error message.
- The following lines contain one record each. Since all fields are given as strings, they are converted automatically to the type of the destination attribute. For attributes of type Boolean, the field must be either NIL or TRUE (case insensitive), otherwise an error message is generated. For attributes of type choice the exact label string must be specified (case sensitive). For reference attributes the record number starting with 1 must be specified. For all other types a value of NIL is used if the field cannot be converted to the required type.
- If you decide to use double quotes then all record fields including the line containing the field names must be surrounded by double quotes.

13.2 Sample Import File

The following sample import file uses `\n` and `\t` for record and field delimiters and double quotes around all fields. The file can be imported into a table with the following attributes:

- Name (string)
- NumChildrens (integer)
- Feminine (Boolean)
- Job (choice)
- Notes (memo)

```
"Name" "NumChildrens" "Feminine" "Job" "Notes"
"Janet Jackson" "???" "TRUE" "Musician" "Latest CD: The velvet rope"
"Bernt Schiele" "???" "NIL" "Scientist" "Research interests:
Robotics, Autonomy and Computer Vision"
"Gerhard" "0" "NIL" "Precision mechanic" ""
```

13.3 Importing Records

To import records into the active table select menu item ‘**Table - Import records**’. This will open a window containing

- a string field for entering the import filename. To the right of this field you find three buttons. Click on the first one to open a file dialog for choosing the filename. The second button starts an external viewer with the entered filename while the third button starts an editor for editing the file contents.
- two string fields for entering the record and field delimiters. You can enter a single character or an escape code by typing `\n`, `\t`, `\f`, `\????` (octal code), or `\x??` (hex code). Delimiter characters must be 7bit ASCII characters.
- a field ‘**Double quotes**’ that can be checked to specify that the fields are surrounded by double quotes.
- a field ‘**Overwrite records**’ that if selected will overwrite existing records with the imported data. This can be useful in case you want to keep the existing records (e.g. because there are references to them) but update them with new information.
- two buttons ‘**Import**’ and ‘**Cancel**’ for leaving the window.

If you press the ‘**Import**’ button, MUIbase will load the specified file and import all found records. If everything went fine and new records were created in the table, MUIbase asks after the import process if you really want to add the newly imported records to the table. At this point you can still cancel the operation. Overwritten records, however, can only be recovered by reverting the project.

If an error occurs while reading the import file then an error message is shown.

If you need a more sophisticated import routine it is recommended to write your own import routine as a MUIbase program.

13.4 Exporting Records

To export records from the active table select menu item ‘**Table - Export records**’. This will open a window containing

- a string field for entering the export filename. Right to this field you find a pop-up button to open a file dialog for choosing the filename.
- two string fields for entering the record and field delimiters. You can enter a single character or an escape code by typing `\n`, `\t`, `\f`, `\????` (octal code), or `\x??` (hex code).
- a field ‘**Double quotes**’ that can be checked to specify that the fields should be surrounded by double quotes.
- a field ‘**Filter**’. If checked only the records that match the currently installed record filter are written to the export file.
- two buttons ‘**Export**’ and ‘**Cancel**’ for leaving the window.

After you pressed the ‘**Export**’ button, MUIbase will open the specified file and write out the records including a header line containing the attribute names. The export feature always writes all attribute fields of a table to the export file.

For a more customized export routine, you can use MUIbase’ query editor (see Chapter 14 [Data retrieval], page 53) or you write your own export function as a MUIbase program.

14 Data Retrieval

For data retrieval MUIbase offers two ways: the programming feature and the query editor.

The programming feature allows you to install buttons in table masks which, when pressed, call program functions. The usage of this feature is described in the structure editor chapter (see Chapter 15 [Structure editor], page 59) and in the chapter about programming MUIbase (see Chapter 16 [Programming MUIbase], page 74).

This chapter describes the usage of the query editor, a dialog where you can enter queries and view the output in a scrolling list-view.

14.1 Select-From-Where Queries

MUIbase offers a select-from-where query similar to the one in SQL database systems. The query allows you to list the record contents from one or more tables. Only records matching certain criteria are included in the output. The (incomplete) syntax of an select-from-where query is

```
SELECT exprlist FROM tablelist [WHERE test-expr]
[ORDER BY orderlist]
```

where *exprlist* is a comma separated list of expressions to be printed (usually the attribute names) or a simple star * matching all attributes of the specified tables, *tablelist* is a comma separated list of tables whose records are examined, *test-expr* is the expression that is tested for each set of records to be included in the output, and *orderlist* is a comma separated list of attributes that defines the order for listing the output. Please note that the WHERE and ORDER BY fields are optional, denoted by the brackets [].

For example, the query

```
SELECT * FROM table
```

lists the attribute contents of all records in the given table.

```
SELECT attr1 FROM table WHERE (LIKE attr2 "*Madonna*")
```

lists the value of the *attr1* field in all records of *table* where the contents of field *attr2* contain the word 'Madonna'.

For more information about the select-from-where query including its full syntax, see Chapter 16 [Programming MUIbase], page 74, for more example see Section 14.6 [Query examples], page 56.

14.2 Query Editor

For entering and running queries, open the query editor by choosing menu item 'Program - Queries'. The query editor is able to manage several queries, however only one query is displayed at a time. The query editor window contains the following items:

- a string input field with an attached pop-up button. The edit-able string field displays the name of the current query. By pressing the pop-up button, a list with further query names together with several buttons appear. You can select one of the listed queries to make it the current one, press the 'New' button to create a new query, press the 'Duplicate' button to get a copy of the selected query, click on the 'Sort' button to sort the list of queries, or press the 'Delete' button to delete the selected query.

For leaving the pop-up window without changing anything, click on the pop-up button again.

- a choice field that allows to assign the query to a table. When assigning a table, MUIbase runs this query when the user selects menu item ‘Table - View all records’ in the corresponding table.
- a ‘Run’ button that compiles and runs the query program and displays the output in the output list-view.
- an ‘Export’ button that opens a dialog (see Section 14.3 [Exporting queries as text], page 54) for exporting the query results to a text file.
- a ‘PDF’ button (on most systems) that opens a dialog (see Section 14.4 [Exporting queries as PDF], page 55) for exporting the query results to a PDF file.
- a ‘Print’ button that opens a dialog (see Section 14.5 [Printing queries], page 55) for printing the results.
- an editor field for entering the query program. Here you usually enter a select-from-where query. However, it is also possible to enter any expression of MUIbase’ programming language. This can be useful if you want to do simple computations or update some fields of a table by using a simple program. Please note that MUIbase automatically surrounds your program expression with a pair of parenthesis, thus you can omit the outermost ones.
- a list-view that displays the output after running the current query. The output is formatted into rows and columns. The title row holds the field names of the select-from-where query (usually the attribute names). The other rows hold the contents of the query result, one set of records per row. Each field is displayed in its own column. By clicking on a column title you can sort the list with respect to this column. A second click onto the same column title reverses the order. On the Amiga you can set a secondary sort column by holding down the *Shift* key when clicking on a title. If you double click on entry in the list and the entry was generated from a record then this record is displayed in the corresponding table mask. This offers an easy way to jump to a certain record in its table mask.

The query editor is a non-modal dialog. This means that you can leave the query editor open and still work with the rest of the application. You can close the query editor at any time by clicking on the close button in the window title bar.

14.3 Exporting Queries as Text

You can export the results of a select-from-where query to a text file by pressing the ‘Export’ button. This will open a window containing

- a string field for entering the export filename. Right to this field you find a pop-up button to open a file dialog for choosing the filename.
- two string fields for entering the record and field delimiters. You can enter a single character or an escape code by typing `\n`, `\t`, `\f`, `\???` (octal code), or `\x??` (hex code).
- a field ‘Double quotes’ that can be checked to specify that the fields should be surrounded by double quotes.
- two buttons ‘Export’ and ‘Cancel’ for leaving the window.

After you pressed the **‘Export’** button, MUIbase will open the specified file and write out the query result including a header line containing the list header. The fields are written in the order of the columns in the list.

14.4 Exporting Queries as PDF

On Windows, Mac OS X, Linux and MorphOS you can export the query results to a PDF file by pressing the **‘PDF’** button.

On Windows, Mac OS X and Linux this opens the standard print dialog where the **‘Print to file’** entry with a **‘PDF’** format is preset. The dialog contains a custom page **‘Font’** where you can specify a font and enable the shrinking of all contents such that they fit into the page width of the selected paper and orientation. After pressing the **‘Print’** button the query results are written to the specified file.

On MorphOS a window is opened that contains the following elements:

- a string field for entering the export filename. Right to this field you find a pop-up button to open a file dialog for choosing the filename.
- a choice field for selecting the paper size.
- a choice field for specifying the orientation (**‘Portrait’** or **‘Landscape’**).
- a choice field for choosing the font with a text field for entering the font size. It is possible to enter fractions, e.g. **‘10.5’**.
- a status field that shows the number of pages and whether the contents fit into the page width.
- two buttons **‘Create PDF’** and **‘Cancel’** for leaving the window.

After pressing the **‘Create PDF’** button, MUIbase opens the specified file and writes out the query result including a header line containing the list header. The fields are written in the order of the columns in the list.

14.5 Printing Queries

After you have run a query you can print the result by clicking on the **‘Print’** button in the query editor.

On Windows, Mac OS X and Linux this opens the standard print dialog. The dialog contains a custom page **‘Font’** where you can specify a font and enable the shrinking of all contents such that they fit into the page width of the selected paper and orientation. After pressing the **‘Print’** button the query results are sent to the selected printer.

On MorphOS the **‘Print’** button opens a similar dialog when exporting queries as PDF (see Section 14.4 [Exporting queries as PDF], page 55). The window contains the following elements:

- a choice field for selecting the paper size.
- a choice field for specifying the orientation (**‘Portrait’** or **‘Landscape’**).
- a choice field for choosing the font with a text field for entering the font size. It is possible to enter fractions, e.g. **‘10.5’**.
- a status field that shows the number of pages and whether the contents fit into the page width.

- two buttons ‘**Create PDF**’ and ‘**Cancel**’ for leaving the window.

After pressing the ‘**Create PDF**’ button, MUIbase generates a temporary PDF file and opens it with the external viewer (see Section 7.1.3 [External viewer], page 33). You can then use the printing facilities in the external viewer for sending the query results to your printer.

On other Amiga systems, a print dialog containing the following items is shown:

- a field ‘**Delimiter**’ where you specify how the columns should be separated. ‘**Spaces**’ pads the fields with space characters. Padding is done on the left or on the right side depending on the type of the field (numbers are padded on the left, text on the right side). ‘**Tabs**’ inserts exactly one tab character between the columns. This can be useful if you want to use the print dialog for exporting records (see below). ‘**Custom**’ allows to specify a custom delimiter string to be printed between fields.
- a field ‘**Font**’ where you specify which font should be used for printing the output. ‘**NLQ**’ stands for near letter quality which should print the output in better quality than ‘**Draft**’.
- a field ‘**Size**’ where you define the character size. ‘**Pica**’ prints in a large font (10 CPI), ‘**Elite**’ in a medium font (12 CPI) and ‘**Condensed**’ in a small font (17 CPI).
- a string field ‘**Init sequence**’ where you can enter a string for initializing your printer. The contents of this field are written directly after opening the printer. For example you can use ‘**\33c**’ as init sequence which resets your printer.
- a field ‘**Indent**’ where you can enter a number of spaces that are used for indenting each output line.
- a field ‘**Headline**’ that, if checked, prints the field names in the first line.
- a field ‘**Escape codes**’. If not checked the output of all escape codes is suppressed which means that the settings of the fields ‘**Font**’ and ‘**Size**’ are ignored and the contents of ‘**Init sequence**’ are not printed. Suppressing the output of all escape codes is useful if you want to generate an ASCII file, e.g. for exporting records.
- a field ‘**Quotes**’ that, if checked, surrounds all fields with double quotes.
- a field ‘**After printing**’ where you can specify how the output should be finished. ‘**Form feed**’ prints a form feed character `\f`. ‘**Line feeds**’ prints a number of line feed characters `\n`. The number of line feeds can be entered in the string field to the right of the ‘**Line feeds**’ button. ‘**Nothing**’ doesn’t write anything to the printer.
- a string field ‘**Output**’ with an attached pop-up button. You can use the pop-up button to open a file dialog for choosing a filename or directly enter the filename into the string field. For writing the output to your printer enter `lpr` (Linux) respectively `PRT:` (Amiga). For other special filenames, see Section 7.2.12 [Program output file], page 37.
- two buttons ‘**Ok**’ and ‘**Cancel**’ for leaving the print dialog.

After you are done with all settings, click on the ‘**Ok**’ button to start the print job.

14.6 Query Examples

To give you an impression of the power of the select-from-where queries this section gives you some sample queries.

Suppose we have two tables 'Person' and 'Dog'. 'Person' has a string attribute 'Name', an integer attribute 'Age', and two reference attributes 'Father' and 'Mother' that refer to the father and mother records in table 'Person'. The table contains the following records:

	Name	Age	Father	Mother
p1:	Steffen	26	p2	p3
p2:	Dieter	58	NIL	NIL
p3:	Marlies	56	NIL	NIL
p4:	Henning	57	NIL	NIL

'Dog' has a string attribute 'Name', a choice attribute 'Color' and a reference attribute 'Owner' that refers to the owner in the 'Person' table. The table contains the following records:

	Name	Color	Owner
d1:	Boy	white	p3
d2:	Streuner	grey	NIL

Given these data the following sample select-from-where queries can be run:

```
SELECT * FROM Person
```

results to:

Name	Age	Father	Mother
Steffen	26	Dieter	Marlies
Dieter	58		
Marlies	56		
Henning	57		

(For the reference attributes the 'Name' field of the referenced record is printed.)

```
SELECT Name "Child", Age,
       Father.Name "Father", Father.Age "Age",
       Mother.Name "Mother", Mother.Age "Age"
FROM Person WHERE (AND Father Mother)
```

results to:

Child	Age	Father	Age	Mother	Age
Steffen	26	Dieter	58	Marlies	56

```
SELECT Name, Color,
       (IF Owner Owner.Name "No owner") "Owner"
```

FROM Dogs

results to:

Name	Color	Owner
Boy	white	Marlies
Streuner	grey	No owner

SELECT a.Name, a.Age, b.Name, b.Age FROM Person a, Person b
WHERE (> a.Age b.Age)

results to:

a.Name	a.Age	b.Name	b.Age
Dieter	58	Steffen	26
Marlies	56	Steffen	26
Henning	57	Steffen	26
Dieter	58	Marlies	56
Henning	57	Marlies	56
Dieter	58	Henning	57

15 Structure Editor

MUIbase has two different operating modes, the record-editing mode, where you enter and browse records, and the structure-editing mode where you define the structure, that is, the tables, attributes and appearance of a project. This chapter describes the structure editor and explains how to manage the structure of a project.

To switch from record-editing to structure-editing mode select menu item ‘**Structure editor**’ in the ‘**Project**’ menu. This closes all windows and opens the structure editor window. To switch back to record-editing mode select menu item ‘**Project - Exit structure editor**’ or simply close the structure editor by clicking on the close button in the window title bar.

The structure editor window is divided into three parts: in the upper left part there is a field ‘**Tables**’ for managing the tables of the project, the lower left part is occupied by a field ‘**Attributes**’ for managing the attributes of a table, and the right part is used by a field ‘**Display**’ for managing the project’s GUI elements.

15.1 Table Management

In the ‘**Tables**’ field of the structure editor you can create, change, delete and sort tables.

15.1.1 Creating Tables

To create a new table press the ‘**New**’ button in the ‘**Tables**’ field. This will open the ‘**New table**’ dialog containing

- a string field for entering the name of the table. Each table must have a unique name that starts with an uppercase letter followed by further letters, digits or underscore characters. Non-ASCII characters like German umlauts are not allowed. Please note that in the user interface for the table it is still possible to display any strings including strings with non-ASCII characters.
- a field ‘**Number of records**’ where you specify how many records the table is going to hold. ‘**Unlimited**’ means that the table can hold any number of records, ‘**Exactly one**’ means that the table can have only one record. The latter one is sometimes useful for controlling the project (see Section 5.2 [Tables], page 18).
- a field ‘**Trigger functions**’ where you can enter the names of two functions. In the ‘**New**’ string field you enter the name of the function that should be called whenever the user wants to create a new record, the ‘**Delete**’ string field holds the name of the function that should be called whenever the user wants to delete a record. You can use the pop-up buttons to the right of the string fields for choosing a function name from a list of all names. If you leave a field empty then default actions are executed (records are created automatically and records are deleted after an optional confirmation dialog). For more information on how to use these trigger functions, including the arguments that are passed to them, see Section 16.29.8 [New trigger], page 146, and Section 16.29.9 [Delete trigger], page 147.
- a check-mark field ‘**Count changes**’ that, if selected, makes any creation or deletion of a record count as a change to the project. If not selected then any change in the table (or in any of the table’s attributes) is ignored.

- a check-mark field ‘Log changes’. If selected, any creation or deletion of a record is recorded in the project log. Otherwise, no change in the table (or in any of the table’s attributes) is ever logged.
- two buttons ‘Ok’ and ‘Cancel’ for leaving the dialog.

When you are done with all settings, press the ‘Ok’ button to create the new table. If you made an error somewhere, e.g. you entered an invalid name, a message window pops up giving you more information about the error you did. If everything goes fine, the ‘New table’ dialog will be closed and the new table is displayed in the structure editor’s table list.

15.1.2 Changing Tables

After you have created a new table you can still change it. Just double-click on the table’s name and the ‘Change table’ dialog pops up. This dialog is similar to the one when creating a table (see Section 15.1.1 [Creating tables], page 59) and allows you to make changes in any field by entering a new value.

When you are done with all changes, press the ‘Ok’ button to leave the dialog.

Please note that you can’t change the number of records from ‘Unlimited’ to ‘Exactly one’ if the table already contains more than one record.

15.1.3 Deleting Tables

To delete a table, click on the table’s name in the structure editor’s table list, then press the ‘Del’ button below the list. Before the table is actually deleted a dialog pops up asking for confirmation. If you confirm this dialog by pressing the ‘Delete’ button, the table is deleted.

A problem occurs if the table is used somewhere in the project’s program. In this case the table can’t simply be deleted but all references to the table must be removed from the program. If the table you want to delete is used in the project’s program then the program editor pops up and displays the first occurrence to the table. You should now modify the program such that no references to this table remain in the program. After you removed a reference you can jump to the next one by pressing the ‘Compile’ button. At any point you can still cancel the whole operation by pressing the ‘Revert’ button and closing the program editor.

15.1.4 Sorting Tables

For sorting the tables in the ‘Tables’ field of the structure editor you have several choices. You can order them manually, that is, you use drag & drop to rearrange a table, or you use the ‘Sort’ button below the list-view which orders the tables alphabetically (‘Sort1’), or according to the order in the list display (‘Sort2’).

15.2 Attribute Management

In the ‘Attributes’ field of the structure editor you can create, copy, change, delete and sort the attributes of the active table in the ‘Tables’ field.

15.2.1 Creating Attributes

To create a new attribute for the active table press the ‘New’ button in the ‘Attribute’ field. This will open the ‘New attribute’ dialog containing

- a string field for entering the name of the attribute. Each attribute in a table must have a unique name that starts with an uppercase letter followed by further letters, digits or underscore characters. Non-ASCII characters like German umlauts are not allowed. Please note that in the user interface it is still possible to display any strings including strings with non-ASCII characters for the attribute.
- a choice field ‘Type’ where you specify the type of the attribute. For more information on attribute types, see Section 5.5 [Attribute types], page 19.
- a section below the ‘Type’ field for specifying type specific settings. For more information about this section, see Section 15.2.2 [Type specific settings], page 61.
- a field ‘Trigger’ where you can enter the name of a function that should be called whenever the user wants to change the contents of the attribute field in a record. You can use the pop-up button to the right of the string field for choosing a name from a list of all function names. If you leave the field empty then a default action is executed, that is, the entered value is simply stored in the attribute field. For more information on how to use the trigger function, including the arguments that are passed to it, see Section 16.29.11 [Attribute trigger], page 148.
- a field ‘Count changes’. If checked, every change to the attribute in a record counts as a change of the project. Uncheck this item, if you want to ignore changes to an attribute. Note that this item is only enabled when also the ‘Count changes’ item in the table has been set (see Section 15.1.1 [Creating tables], page 59).
- a field ‘Log changes’, that, if checked, logs any change made to the attribute in a record. Note that this item is only enabled when also the ‘Log changes’ item in the table has been set (see Section 15.1.1 [Creating tables], page 59).
- two buttons ‘Ok’ and ‘Cancel’ for leaving the dialog.

When you are done with all settings, press the ‘Ok’ button to create the new attribute. If you made an error somewhere, e.g. you entered an invalid name, a message window pops up giving you more information about the error you did. If everything goes fine, the ‘New attribute’ dialog will be closed and the new attribute is displayed in the structure editor’s attribute list.

15.2.2 Type Specific Settings

In the type specific section the following settings can be specified:

- For attributes of type string you have
 - an integer field ‘Max length’ for entering the maximum string length for this attribute field.
 - a string field ‘Initial value’ for specifying the value that is used for initializing the attribute field. Any string up to the specified maximum length can be entered here.
- For attributes of type integer, real, date, and time the type specific section offers

- a field ‘Initial value’ where you specify the value for initializing the attribute field. You can choose between ‘NIL’ and ‘other’. If you select ‘other’ then you should enter the initial value into the string field on the right.
- a string field ‘NIL string’ where you enter the string that should be displayed when the attribute field holds the NIL value.
- For Boolean attributes the type specific section contains a field ‘Initial value’ where you can choose between ‘NIL’ and ‘TRUE’ for the initial value.
- The type specific section for choice attributes offers
 - a button ‘Edit labels’ for opening the ‘Edit labels’ window where you can enter the label strings for the choice field (see Section 15.2.3 [Label editor], page 62).
 - a choice field ‘Initial value’ for specifying the value for initializing the attribute field.
- For reference attributes the type specific section contains
 - a list-view displaying all tables for specifying to which table the reference should be made. Click on the table the attribute is going to reference.
 - a field ‘Auto show’. If checked, the referenced table gets updated automatically with the referenced record whenever the user switches to another record.
 - a field ‘Filter’. If checked, the reference filter of this attribute is turned on. See Section 10.2 [Reference filter], page 45, for more information about this feature.

Reference attributes always have the NIL value as initial value.

- The type specific section for virtual attributes contains a string field ‘Compute’ where you enter the name of a function that should be called for calculating the value of the attribute. You can use the attached pop-up button for selecting a name from a list of all function names. For more information on how to use this function, see Section 16.29.12 [Programming virtual attributes], page 149.
- Memo and button attributes do not have any type specific settings. The initial value for memo attributes is an empty string.

15.2.3 Label Editor

Whenever you have to define a list of labels, e.g. the list of labels for a choice attribute, the label editor comes into place. The label editor is a window containing:

- a list-view displaying the current list of labels. You can click on a label to make it the active one. The active label is also displayed in the string field below the list-view. You can use drag & drop to rearrange the labels.
- a string field ‘Label’ that displays the active label and allows changing it. The changes do only have effect after you pressed the **Enter** key. If there is currently no active label then pressing **Enter** inserts new labels into the list.
- a button ‘New’ that deactivates the current label which allows entering new labels into the ‘Label’ string field.
- a button ‘Remove’ that removes the active label from the list.
- a button ‘Sort’ for ordering the list of labels alphabetically.
- two buttons ‘Ok’ and ‘Cancel’ for leaving the label editor.

After you entered all labels or made changes to them, press the ‘Ok’ button to leave the window.

15.2.4 Copying Attributes

In case you need a lot of similar attributes, it is possible to copy an attribute. Just select the desired attribute and press the ‘Copy’ button below the attribute list. This opens the ‘Copy attribute’ dialog where the settings of the selected attribute are displayed. Change some of the fields, e.g. the name, and then press ‘Ok’ for creating a copy of the attribute.

15.2.5 Changing Attributes

After you have created a new attribute it is still possible to change some settings of it. Just double-click on the attribute’s name and the ‘Change attribute’ dialog pops up. This dialog is similar to the one when creating an attribute (see Section 15.2.1 [Creating attributes], page 61) and allows you to make changes in some fields. The fields that cannot be changed, e.g. the attribute type, are displayed ghosted.

The following notes should be taken into account when changing an attribute.

- The type of an attribute cannot be changed. If you ever want to change the type of an attribute, it is best to create a new one of the desired type and copy the record contents from the old attribute to the new one by entering a simple MUIbase program in the query editor (see Section 14.2 [Query editor], page 53).
- If you change the initial value of an attribute then only new records will get the new value for initializing the record.
- For choice attributes you should be careful when changing its labels. The labels are only used for displaying the choice field contents, internally, numbers are stored that are used as an index into the list of labels. Thus, if you change the order of labels, you actually don’t change the internal number but the label which is displayed for it! Therefore you should not change the order of labels after you created a choice attribute. Appending new labels to the end of the label list, however, doesn’t make any problems. For a more flexible way of having a choice-like field where you can also change the order of labels, use a string attribute together with the ‘List-view pop-up’ feature (see Section 15.3.3 [Attribute object editor], page 66).
- The referenced table of a reference attribute cannot be changed.

When you are done with all changes, press the ‘Ok’ button to leave the dialog.

15.2.6 Deleting Attributes

To delete an attribute, click on it’s name in the structure editor’s attribute list and press the ‘Del’ button below the list. Before the attribute is actually deleted a dialog pops up asking for confirmation. If you confirm this dialog by pressing the ‘Delete’ button, the attribute is deleted.

A problem occurs if the attribute is used somewhere in the project’s program. In this case the attribute can’t simply be deleted but all references to it must be removed from the program. If the attribute you want to delete is used in the project’s program then the program editor pops up and displays the first occurrence to this attribute. You should now modify the program such that no references to this attribute remain in the program. After you removed a reference you can jump to the next one by pressing the ‘Compile’ button.

At any point you can still cancel the whole operation by pressing the ‘Revert’ button and closing the program editor.

15.2.7 Sorting Attributes

For sorting the attributes in the ‘Attributes’ field of the structure editor you have several choices. You can order them manually, that is, you use drag & drop to rearrange an attribute, or you use the ‘Sort’ button below the list-view which orders the attributes alphabetically (‘Sort1’) or according to the order in the list display (‘Sort2’).

15.3 Display Management

In the ‘Display’ field of the structure editor you specify how the database elements should be arranged in the user interface. The field consists of a choice field, a list-view and several buttons.

15.3.1 Display Field

The display field contains the following items:

- a choice item with two settings, ‘Table mask’ and ‘Main window’. In ‘Table mask’ you specify how the attributes of the active table are arranged in the user interface. In ‘Main window’ you specify how the tables are arranged.
- a list-view that displays the current specification of the user interface. The list is organized as a tree. Items that have an arrow to its left are composite GUI objects and can be opened and closed by (double-) clicking on the arrow symbol. A double-click on the item itself opens a window for editing its settings. All GUI objects that have the same parent object are layed out in the same way (either vertically or horizontally). How the layout is done is determined by the parent GUI object: tables and windows layout their elements vertically, groups layout their elements according to the settings in the group editor (see Section 15.3.8 [Group editor], page 71).
- a button ‘+’ (‘Add’) for adding the active table or the active attribute (depending on the state of the display choice field) to the display list-view. Usually tables and attributes are added to the display list-view automatically when you create them.
- a button ‘-’ (‘Rem’) for removing the active item from the display list-view. If you remove a table then the whole table form is removed from the user interface, thus you can’t see the table in the project’s GUI. This way you can hide entire tables. If you remove an attribute from the display list-view then the attribute doesn’t appear in the project’s GUI. This is useful for hiding attributes.
- two buttons ‘Up’ and ‘Down’ for moving the active item one field up, respectively down, in the display list-view.
- two buttons ‘In’ and ‘Out’ for moving the active item one hierarchical level down or up in the display list-view.
- a button ‘Text’ for adding a text object to the display list-view (see Section 15.3.5 [Text editor], page 70).
- a button ‘Image’ for adding an image object (see Section 15.3.6 [Image editor], page 71).
- a button ‘Space’ for putting space between the other objects (see Section 15.3.7 [Space editor], page 71).

- a button **‘Balance’** for adding a balance object to the display list-view. The balance object is useful for controlling the size of the other GUI objects.
- a button **‘Group’** for adding a group object to the display list-view. Before you press the **‘Group’** button you can multi-select the items in the list-view that should be moved into the new group. See Section 15.3.8 [Group editor], page 71, for more information about setting up a group object.
- a button **‘Register’** for adding a register group to the display list-view. As for group objects, you can multi-select the GUI objects that should be moved into the new register group. For more information about setting up a register group see Section 15.3.9 [Register group editor], page 72.
- a button **‘Window’** for adding a new window to the display list-view. As before, you can multi-select the GUI objects that should be moved into the new window. For more information about setting up a window, see Section 15.3.10 [Window editor], page 72.

For more information about the GUI elements, including their usage, see Section 5.9 [User interface], page 25.

15.3.2 Table Object Editor

When adding a table a default display object is created. To change the settings of the table object, double click the table in the **‘Display’** list and the **‘Display table’** window appears. The window has three sections that are separated into the tabs **‘General’**, **‘Panel’** and **‘Record’**.

The **‘General’** section contains the following items:

- a numerical field **‘Weight’** for specifying the weight of the object. The value of this field determines how much space, relative to the other objects, the table gets in the final window layout.
- a field **‘Background’** with a check-mark field **‘Default’** for specifying how the background of the table should look like. If you check the **‘Default’** field then a default background is used, otherwise you can click on the **‘Background’** field to open a window for specifying a custom background.
- a check-mark field **‘Has panel’** that specifies whether a panel should be displayed at the top of the table. Uncheck this field for hiding the panel. For more information about panels, see Section 5.9.3 [Panels], page 26.

The **‘Panel’** section is only enabled if the **‘Has panel’** field has been checked. It contains the following items:

- a string field **‘Title’** for entering a title that should be displayed in the panel header.
- a string field **‘Font’** with a pop-up button for selecting a font for the title. If you leave the field empty, a default font is used.
- a field **‘Background’** with a check-mark field **‘Default’** for specifying the background of the panel header. If you check the **‘Default’** field then a default background is chosen. Otherwise you can click on the **‘Background’** button to open a window for specifying a custom background.
- a field **‘Num/All’**. If checked the number of the current record and the number of all records are displayed in the right part of the panel header.

- a field **Filter** that, if checked, adds a filter button to the panel header. With the filter button you can turn on and off the record filter of the table. If you don't check this field then the menu item **Table - Change filter** will also be disabled for this table, thus you can't enter a filter expression for the table. For more information about record filters, see Section 10.1 [Record filter], page 44.
- a field **Arrows** for adding two arrow buttons to the table mask. The arrow buttons allows you to browse through the records of the table. If you don't check this field then you can't browse the records of this table and all sub menu items of menu item **Goto record** and the menu items **Search for**, **Search forward**, and **Search backward** in menu **Table** are disabled.

The **Record** section allows to specify a record description. The record description is used when creating log entries and in list popups for selecting a record. It should be a short but unique identification. The section contains the following items:

- a choice field **Description** that can be set to either **Fields** or **Computed**.
- if **Description** is set to **Fields** then a list of attributes of the table are shown. You can choose any of the items for the record description. If you select **Record number** than the record number of a record is included in the display. Multiple items can be selected and you can rearrange the order of items by drag and drop.
- if **Description** is set to **Computed** then a field **Compute** is shown for entering a function that computes the record description. The function can either return a single expression or a list of expressions (see Section 16.29.14 [Compute record description], page 150).
- a check-mark field **Use multi-column list** for specifying a preference of how to arrange the list items when presented in a list-view.

Below the tab-separated sections there are two buttons **Ok** and **Cancel** for leaving the window. After you are done with all settings, click on the **Ok** button to close the window.

15.3.3 Attribute Object Editor

When you add an attribute to the display list-view, a default GUI object is created for it. To change the settings of the attribute object, a double click on it opens the **Display attribute** window. This window contains several items depending on the type of the attribute. The following items are included for most attribute types:

- a string field **Title** for entering a title that is displayed near the attribute object (or, for buttons, inside the object). If you leave this field empty then no title is displayed.
- a choice field **Position** for specifying where the title (if any) is placed relative to the attribute object. You can choose between **Left**, **Right**, **Top**, and **Bottom**.
- a string field **Shortcut** for entering a letter than can be used together with the **Alt** key (Windows, Mac OS and Linux) or the **Amiga** key to activate the object.
- a field **Home**. If checked, this attribute object becomes the home object. The home object is used as the object where the cursor is set on whenever a new record is allocated. This is quite useful if you always want to start entering data into the same attribute whenever you create a new record. If you mark an attribute object as the home object then all other attribute objects in the same table loose this property.

- a field **‘Tab chain’**. If checked the object is part of the focus chain that can be cycled through by pressing the **Tab** key. Uncheck this item if you want to skip over the element.
- a field **‘Read only’** that, if checked, gives the object a read only status. This means that you can only read its contents but can’t edit them. Note however, that if you add a pop-up button to the object, the contents can still be changed by the selections offered in the pop-up.
- a choice field **‘Alignment’** for specifying how the attribute contents should be presented in the object. You can choose between **‘Center’**, **‘Left’** and **‘Right’** for displaying the contents centered, flushed left, or flushed right.
- an area **‘Enabled/disabled’**. If **‘Always enabled’** is selected then the object is always enabled independent of the record shown. **‘Disabled in initial’** disables the object in the initial record but enables it otherwise. If **‘Compute enabled’** is chosen then a function for computing the enabled state of the object can be entered to the right. The function does not take any arguments. If it returns NIL then the object is disabled, otherwise enabled. In case the compute function is left empty or cannot be found, the object gets disabled. For more information on how to use this trigger function, see Section 16.29.13 [Compute enabled function], page 149.
- a numerical field **‘Weight’** for specifying the weight of the object. The value of this field determines how much space, relatively to the other objects, the object gets in the final window layout. For most attribute types this field only affects the horizontal size of the object as most objects have a fixed height. For a Memo attribute, for example, it also affects the vertical size.
- a field **‘Font’** for selecting the font used for displaying the attribute contents. If you leave the field empty, a default font is used.
- a field **‘Background’** with a check-mark field **‘Default’** for specifying how the background of the attribute should look like. If you check the **‘Default’** field then a default background is used, otherwise you can click on the **‘Background’** field to open a window for specifying a custom background.
- an editor field **‘Bubble help’** where you can enter text that should be displayed as the bubble help information for this attribute object.
- two buttons **‘Ok’** and **‘Cancel’** for leaving the window.

If you are done with all settings, press the **‘Ok’** button to leave the window.

15.3.4 Type Specific Settings

Besides the above items, the following type-specific items are present:

- for attributes of type string there is an **‘Extras’** page which contains:
 - a field **‘Display picture’** that, if checked, attaches an image field to the string attribute for displaying the image whose filename is taken from the attribute contents. The image field is put above the string field. If you don’t check this item then the settings of the fields **‘Title at string field’**, **‘Hide string field’**, and **‘Size’** are meaningless.
 - a field **‘Title at string field’**. If checked, the title of the attribute object is placed to the left of the string field, thus the image field gets more space in the

window. If you don't check this field then the title is placed next to the image field.

- a field **'Hide string field'** for removing the string field from the user interface. If checked, only the image field is displayed.
 - a field **'Size'** for specifying how size-handling is done for the image area. If **'Resizable'** is active, the object can be resized and might become larger than the size of its image. **'Fixed'** sets the object's size to the size of the image. If the image sizes vary from record to record then the object is resized accordingly every time. **'Scrollable'** adds two scrollers to the object allowing to view images that are larger than the visible region. If **'Scaled'** is activated then the image is scaled to the size of the display object. **'Aspect-scaled'** also scales the image but preserves its aspect ratio.
 - a field **'File pop-up'** that, if checked, adds a pop-up button to the right of the string field. This buttons serves to open a file dialog for choosing a filename.
 - a field **'Font pop-up'** for adding a pop-up button that opens a font dialog.
 - a field **'List-view pop-up'**. If checked, a pop-up button is attached to the right of the string field for opening a list-view pop-up where you can choose a string from a list. The label strings for the list-view pop-up are defined to the right of the **'List-view pop-up'** field. The label items can be either **'Static'** or **'Computed'**. If **'Static'** is chosen then the list of strings can be entered in the label editor which is opened after pressing the **'Edit labels'** button. For more information about the label editor, see Section 15.2.3 [Label editor], page 62. If **'Computed'** is chosen then a trigger function can be entered in the **'Compute'** field which is called whenever the pop-up button is pressed. This function should return a memo text with one label string per line, or NIL for an empty list (see Section 16.29.16 [Compute list-view labels], page 151). Only one of the fields **'File pop-up'**, **'Font pop-up'** and **'List-view pop-up'** can be made active.
 - a field **'View'** that, if checked, adds a button to the right of the string field for launching an external viewer with the attribute contents as argument. This can be useful if you store filenames in the attribute and want to display the contents of a file by starting an external viewer. The external viewer can be specified in menu item **'Preferences - External viewer'** (see Section 7.1.3 [External viewer], page 33).
- for attributes of type choice there is a field **'Kind'** where you choose whether the attribute contents should be displayed by a **'Cycle button'** or by a set of **'Radio buttons'**. If you select **'Cycle button'** then you can set the title position to one of **'Left'**, **'Right'**, **'Top'**, or **'Button'**. If you select **'Radio buttons'** then two check mark items **'Frame'** and **'Horizontal'** allow drawing a border around the radio buttons and specifying a horizontal layout.
 - for attributes of type real there is an integer field **'Num decimals'** where you can enter the number of decimals for displaying the floating point values.
 - for attributes of type time there is a choice field **'Format'** for choosing how time values are displayed and entered. You can select between **'HH:MM:SS'**, **'MM:SS'** and **'HH:MM'**. If **'HH:MM'** is chosen, the number of seconds are discarded for display and single numbers on input are regarded as the number of minutes.

- for reference attributes there is an ‘Extras’ page that contains the following items:
 - a ‘Display’ section where you enter a record description which specifies the contents of a referenced record to be displayed. See Section 15.3.2 [Table object editor], page 65, for information on how to setup a record description. Note that the ‘Description’ choice field also offers a ‘From table’ entry. If selected, the settings of the table object are used for displaying a referenced record.
 - an area ‘Pop-up’ where you specify which records of the referenced table should be made available for selection in the pop-up of the reference field and how they should be displayed. If ‘Records’ is set to ‘All’ then all records are available. If ‘Records’ is set to ‘Match filter’ then only the records of the referenced table that match the currently installed filter are available. If ‘Records’ is set to ‘Computed’ then a function for computing the set of records can be entered in the ‘Compute’ field. This trigger function should return a list that is searched for the occurrence of records of the referenced table. Any such record found is shown in the pop-up. Non-record items are ignored. See Section 16.29.17 [Compute reference records], page 151, for more information about this function. In addition to the records specified by the ‘Records’ setting, the initial record and the currently shown record in the referenced table can be added to the pop-up list by activating the ‘Initial record’ and ‘Current record’ items respectively.
 - a field ‘Show’. If checked then the GUI object for displaying the reference is created as a button. Clicking on this button will show you the referenced record in the table mask of the referenced table. For this the window the referenced table resides in is opened and brought to front if necessary.
 - a field ‘Auto show’ that, if checked, adds a button to the right of the reference field for turning auto show mode on and off for this attribute. When turned on, the referenced table gets updated automatically with the referenced record whenever the user switches to another record.
 - a field ‘Filter’ that, if checked, adds a button to the right of the reference field for turning on and off the reference filter for this attribute. See Section 10.2 [Reference filter], page 45, for more information about reference filters.
- for virtual attributes the attribute object editor contains an ‘Extras’ page with the following items:
 - a choice field ‘Kind’ where you specify how the contents of the virtual attribute should be displayed. You can choose between ‘Boolean’ that uses a check-mark field for displaying Boolean values, ‘Text’ that uses a text field for displaying one line of text (including date, time, and numerical values), and ‘List’ which uses a list-view for displaying a list of lines (e.g. the result of a select-from-where query).
 - if you set the ‘Kind’ field to ‘Text’ then two further fields are available: ‘Alignment’ for specifying how the attribute contents should be presented and ‘Num decimals’ for entering the number of decimals that should be used if the attribute contents are of type real.
 - if the ‘Kind’ field has been set to ‘List’ then further fields ‘Show titles’, ‘Tab chain’ and ‘On double click’ are available. If ‘Show titles’ is checked, the first line of the attribute contents is displayed as a title row in the list-view. Otherwise no title row is displayed and the first line is ignored. If ‘Tab chain’ is checked, the

object is part of the focus chain that can be cycled through by pressing the **Tab** key. Uncheck this item if you want to skip over the element. In ‘**On double click**’ you can specify which action should take place when the user double-clicks a list item. ‘**Do nothing**’ ignores the double click. ‘**Show record**’ displays the record corresponding to the clicked item in the corresponding table view. If you select ‘**Call trigger**’ then the name of a trigger function can be entered to the right. This trigger function is called on each double click. For more information about the trigger function, including the arguments that are passed to it, see Section 16.29.15 [Double click trigger], page 150.

- a field ‘**Auto update**’. If checked, the virtual attribute is recomputed automatically whenever a dependent item changes. This includes switching to a different record in a dependent table, changing a dependent attribute, adding or deleting a record in a dependent table, changing the user/admin mode of the project, or recompiling the project program. The dependencies for the virtual attribute are obtained automatically from the virtual attribute’s compute function. Use menu item ‘**Project - Export structure**’ for viewing all obtained dependencies (you might need to recompile the project’s program in order to update the dependencies when you turn this feature on). Note that the virtual attribute is recomputed irrespective of the record a dependent attribute is changed in and irrespective of whether the dependent attribute’s value was changed in the user interface or during a program execution. However, the auto-updating of virtual attributes usually happens only after all other program executions are completed. If ‘**Auto update**’ is unchecked, the value of the virtual attribute is only computed when it is explicitly queried or set in a program function.
- For buttons there are the following additional fields:
 - a choice field ‘**Kind**’ where you choose between ‘**Text button**’ and ‘**Image button**’.
 - if you set the button kind to ‘**Text button**’ then further fields ‘**Title**’, ‘**Font**’, ‘**Background**’ and ‘**Default**’ appear for entering the text to be displayed in the button, the font used for displaying the text, and the background settings.
 - if the button kind has been set to ‘**Image button**’ then a field ‘**Image**’ for specifying the image to be displayed and a field ‘**Size**’ for specifying the size-handling of the image button are offered.

15.3.5 Text Editor

When you add a text object to the display list-view, or when you change one by double clicking on it, a window ‘**Text**’ is opened. This window contains the following items:

- a string field ‘**Title**’ for entering the text that should be displayed.
- a numerical field ‘**Weight**’ for specifying the horizontal weight of the text object.
- a choice field ‘**Font**’ for specifying the font of the text. If you leave this field empty, a default font is used.
- two fields ‘**Background**’ and ‘**Default**’ for specifying the background settings of the text object.
- two buttons ‘**Ok**’ and ‘**Cancel**’ for leaving the window.

When you are done with all settings, press the ‘**Ok**’ button to leave the window.

15.3.6 Image Editor

The image editor appears when you add a new image object or double click on an existing one. It contains the following items:

- a field **‘Weight’** for specifying the weight of the image object in the final window layout.
- a field **‘Image’** for specifying the image that should be displayed.
- a field **‘Size’** where you specify how resize-handling should be done. If you select **‘Resizable’** then the image object can be resized. **‘Fixed’** sets the object size to the size of the displayed image.
- two buttons **‘Ok’** and **‘Cancel’** for leaving the window.

When you are done with all settings, click on the **‘Ok’** button to close the window.

15.3.7 Space Editor

After you have added a space object to the display list-view, you can change its default settings by double clicking on it. This will open the **‘Space’** window containing the following items:

- a field **‘Delimiter’** that, if checked, displays a vertical or horizontal bar (depending on the layout of the parent object) in the center of the space object. This is useful for separating parts in the window layout.
- a numerical field **‘Weight’** for specifying the weight of the object.
- two fields **‘Background’** and **‘Default’** for specifying the background settings.
- two buttons **‘Ok’** and **‘Cancel’** for leaving the window.

After you are done with all settings, press the **‘Ok’** button to close the window.

15.3.8 Group Editor

After you have added a group object to the display list-view, you can change its settings by double clicking on it. This will open the **‘Group’** window offering the following items:

- a string field **‘Title’** for entering a title string that should be displayed centered above the group. If you leave this field empty then no title is displayed.
- a numerical field **‘Weight’** for specifying the weight of this object.
- two fields **‘Background’** and **‘Default’** for specifying the background settings.
- a field **‘Border’** that, if activated, draws a border frame around the group.
- a field **‘Horizontal’**. If checked, the layout of the group is done horizontally and the group is listed in the display list-view as **‘HGroup’**. Otherwise the group is organized vertically and the display list-view will show a **‘VGroup’** for this group.
- a field **‘Spacing’** that, if checked, adds some space between the group’s child objects. Otherwise no space is put between the objects.
- two buttons **‘Ok’** and **‘Cancel’** for leaving the window.

When you are done with all settings, press the **‘Ok’** button to leave the window.

15.3.9 Register Group Editor

Double click on a register group object in order to change its settings. This will open the ‘Register group’ window offering the following items:

- a numerical field ‘Weight’ for specifying the weight of this object.
- an area ‘Labels’ for specifying the label of each register page. You should specify exactly the same number of labels as there are elements in the register group. For more information on how to enter and edit the labels, see Section 15.2.3 [Label editor], page 62.
- two buttons ‘Ok’ and ‘Cancel’ for leaving the window.

When you are done with all settings, press the ‘Ok’ button to leave the window.

15.3.10 Window Editor

To change the settings of a window object, double click the window object. This will open the window editor containing the following items:

- a string field ‘Title’ where you enter a string that should be displayed in the window title bar and in the optional window button.
- a string field ‘Id’ (Amiga only) which can hold up to four characters defining the MUI window id. If an id is entered, the window position and size can be saved using MUI’s snapshot window facility. Note that all ids defined within MUIbase should be unique. If you accidentally reuse an already taken id then the windows will share the same settings for their window dimensions. Ids beginning with an underscore ‘_’ are reserved for internal use. If you leave the field empty then no MUI window id is set and the window dimensions are stored in the project file. The main window always has the first four characters of the project name as its window id. Specifying an window id is useful if a project is edited under different system configurations as the window positions are then taken from the individual configuration.
- a field ‘Button’ that, if checked, places a button for opening the window into the parent window. If this item is not checked then the window can only be opened from a MUIbase program using the SETWINDOWOPEN function (see Section 16.21.4 [SETWINDOWOPEN], page 135). The following items specify the appearance of the window button.
- a string field ‘Shortcut’ where you enter the shortcut for activating the window button.
- an area ‘Enabled/disabled’. If ‘Always enabled’ is selected then the window button is always enabled. ‘Disabled in initial’ disables the button if it is inside a table and the table shows its initial record, otherwise it is enabled. If ‘Compute enabled’ is chosen then a function for computing the enabled state of the window button can be entered to the right. The function does not take any arguments. If it returns NIL then the button is disabled, otherwise enabled. In case the compute function is left empty or cannot be found, the window button gets disabled. For more information on how to use this trigger function, see Section 16.29.13 [Compute enabled function], page 149. Additionally if the field ‘Close window when disabled’ is checked then the window is closed automatically when the button gets disabled.
- a numerical field ‘Weight’ for specifying the weight of the window button.

- a field 'Font' for selecting the font of the window button. If you leave the field empty, a default font is used.
- two fields 'Background' and 'Default' for specifying the background settings of the window button.
- two buttons 'Ok' and 'Cancel' for leaving the window.

When you are done with all settings, press the 'Ok' button to close the window.

15.4 Export Structure

Sometimes it is useful to get an overview of all tables and attributes of a project, e.g. when you want to write a MUIbase program. You can do this by selecting menu item 'Project - Export structure'. This will ask you for a filename where the list of tables and attributes should be written to.

The output will first list the project name, followed by all tables in this project. For each table all attributes including their types and their optional trigger functions are listed. For virtual attributes also the dependencies for automatically updating the value of the virtual field are listed.

16 Programming MUIbase

This chapter (the largest in this manual) describes the programming language of MUIbase, including all available functions. This chapter, however, is not intended as a general guide about programming. You should be familiar with the basics about programming and should already have written some small (and correctly working :-)) programs.

16.1 Program Editor

To enter a program for a project, open the program editor by selecting menu item ‘**Program - Edit**’. If you are using the setting program source internal (see Section 7.2.6 [Program source], page 35), this will open the ‘**Edit program**’ window containing:

- a text editor field where you edit the project program.
- a button ‘**Compile & close**’ for compiling the program and, on successful compilation, leaving the program editor.
- a button ‘**Compile**’ to compile the program. If your program contains an error somewhere then an error description is put into the window title and the cursor is set on the faulty location.
- a button ‘**Revert**’ that reverts all changes since the last successful compilation.

The program editor is a non-modal window. You can leave the window open and still work with the rest of the application. You can close the editor at any time by clicking into its window close button. If you have done changes since the last successful compilation then a dialog pops-up asking for confirmation to close the window.

In case you have set menu item ‘**Program - Source**’ to ‘**External**’ the external editor (see Section 7.1.2 [External editor], page 32) is launched with the filename of the external source file when choosing ‘**Program - Edit**’. This allows you to edit the program source using your favorite editor (see Section 16.2 [External program source], page 74).

You can also compile a project’s program without opening the program editor by choosing menu item ‘**Program - Compile**’. This can be useful if you e.g. do changes to an external include file and want to incorporate these changes in the project’s program.

16.2 External program source

By choosing menu item ‘**Program - Source - External**’ and entering a filename you can make the program source of a project externally available. This allows you to load the program source into your favorite editor for programming.

If compilation is successful, the compiled program is set as the project’s program and used when executing trigger functions. When you save a project, the last successfully compiled program is store with the project inside the project file. Thus, after saving and closing a project, the external source is no longer needed actually. You can specify if unneeded external source files should be deleted automatically by checking menu item ‘**Preferences - Cleanup external program source**’.

The status of menu item ‘**Program - source**’ is stored with the project. If you re-open a project that uses the external source feature, the external source file is created after opening the project. If the external source file already exists and is different from the version stored inside the project, a dialog asks for confirmation before overwriting the file.

On the Amiga you can send the `compile` command to MUIbase' ARexx port from your editor. MUIbase then reads the external program source, compiles it, and returns the compile status with an optional error message containing filename, line and column, and an error description. This allows you to place the cursor at the exact location of where a compile error occurred. See Section 17.9 [ARexx compile], page 155, for details on return values and error format.

16.3 Preprocessing

MUIbase programs are pre-processed similar to a C compiler preprocessing a C source file. This section describes how to use the preprocessing directives.

All directives start with a hash symbol `#` which should be the first character on a line. Space or tab characters can appear after the initial `#`.

16.3.1 `#define`

```
#define name string
```

Defines a new symbol with the given name and contents. The symbol *string* can be any text including spaces and ends at the end of line. If *string* does not fit on one line you can use further lines by using a backslash character `\` at the end of each line (except for the last one). If the symbol *name* does occur in the remaining source code then it will be replaced by the contents of *string*.

Example: `'(PRINTF "X is %i" X)'` prints `'X is 1'` (Occurrences of *name* in strings are not altered.)

The replacement of defined symbols is done syntactically which means that you can replace symbols with any text, e.g. you can define your own syntax like in the following example:

```
#define BEGIN (
#define END )

BEGIN defun test ()
    ...
END
```

The replacement string of a definition may contain another symbol that has been defined with the `#define` directive to allow nested definitions. However there is an upper limit of 16 nested definitions.

See also `#undef`, `#ifdef`, `#ifndef`.

16.3.2 `#undef`

```
#undef name
```

Removes the definition of symbol *name*. If *name* has not been defined, nothing happens.

See also `#define`, `#ifdef`, `#ifndef`.

16.3.3 `#include`

```
#include filename
```

Reads in the contents of *filename* (a string surrounded with double quotes) at this location. MUIbase searches in the current directory and in the directory specified in the preferences (see Section 7.2.11 [Program include directory], page 37) for loading the file. The file contents are processed by the compiler as if they were part of the current source code.

An external file may include one or more other external files. However there is a limit of 16 nested `#include` directives. To protect files from including them more than once, you can use conditional compilation.

Be careful when moving source code to external files! Debugging and tracking down errors is much harder for external files. Move only well tested and project independent code to external files.

16.3.4 `#if`

`#if const-expr`

If the given constant expression results to non-NIL then the text up to the matching `#else`, `#elif`, or `#endif` is used for compilation, otherwise (the expression results to NIL) the text up to the matching `#else`, `#elif`, or `#endif` is discarded for compilation.

Currently you can only use TRUE and NIL as constant expressions.

See also `#ifdef`, `#ifndef`, `#elif`, `#else`, `#endif`.

16.3.5 `#ifdef`

`#ifdef name`

If the given symbol has been defined with a `#define` directive then the text up to the matching `#else`, `#elif`, or `#endif` is used for compilation, otherwise it is discarded.

See also `#if`, `#ifndef`, `#elif`, `#else`, `#endif`.

16.3.6 `#ifndef`

`#ifndef name`

If the given symbol has not been defined with a `#define` directive then the text up to the matching `#else`, `#elif`, or `#endif` is used for compilation, otherwise it is discarded.

See also `#if`, `#ifdef`, `#elif`, `#else`, `#endif`.

16.3.7 `#elif`

`#elif const-expr`

Any number of `#elif` directives may appear between an `#if`, `#ifdef`, or `#ifndef` directive and a matching `#else` or `#endif` directive. The lines following the `#elif` directive are used for compilation only if all of the following conditions hold:

- The constant expression in the preceding `#if` directive evaluated to NIL, the symbol name in the preceding `#ifdef` is not defined, or the symbol name in the preceding `#ifndef` directive was defined.
- The constant expression in all intervening `#elif` directives evaluated to NIL.
- The current constant expression evaluates to non-NIL.

If the above conditions hold then subsequent `#elif` and `#else` directives are ignored up to the matching `#endif`.

See also `#if`, `#ifdef`, `#ifndef`, `#else`, `#endif`.

16.3.8 `#else`

`#else`

This inverts the sense of the conditional directive otherwise in effect. If the preceding conditional would indicate that lines are to be included, then lines between the `#else` and the matching `#endif` are ignored. If the preceding conditional indicates that lines would be ignored, subsequent lines are included for compilation.

Conditional directives and corresponding `#else` directives can be nested. However there is a maximum nesting count limit of 16 nested conditional directives

See also `#if`, `#ifdef`, `#ifndef`, `#elif`, `#endif`.

16.3.9 `#endif`

`#endif`

Ends a section of lines begun by one of the conditional directives `#if`, `#ifdef`, or `#ifndef`. Each such directive must have a matching `#endif`.

See also `#if`, `#ifdef`, `#ifndef`, `#elif`, `#else`.

16.4 Programming Language

MUIbase uses a programming language with a lisp-like syntax. Indeed several constructs and functions have been adopted from standard lisp. However, MUIbase is not fully compatible to standard lisp. Many functions are missing (e.g. destructive commands) and the meaning of some commands is different (e.g. the `return` command).

16.4.1 Why Lisp?

The advantage of a lisp-like language is that you can program in both, a functional and an imperative way. Functional languages are getting quite popular in mathematical applications. The basic concept in functional languages is the use of expressions. Functions are defined in a mathematical way and recursion is used heavily.

Imperative programming languages (e.g. C, Pascal, Modula) use an imperative description on how to compute things. Here, the state is the basic concept (e.g. variables) and a program computes its output by going from one state to another (e.g. by assigning values to variables).

Lisp combines both techniques and therefore you can choose in which way you want to implement things. Use the one which is more appropriate for the specific problem or which you like more.

16.4.2 Lisp Syntax

A lisp expression is either a constant, a variable, or a function application. For calling functions, lisp uses a prefix notation. The function and its arguments are surrounded by parenthesis. For example, to add two values `a` and `b`, you write

```
(+ a b)
```

All expressions return a value, e.g. in the above example the sum of **a** and **b** returned. Expressions can be nested, that is, you can place an expression as a sub-expression into another one.

Function evaluation is done by using a call-by-value scheme, this means that the arguments are evaluated first before a function is called.

If not stated otherwise, all functions are strict, that is, *all* arguments of a function are evaluated before the function is called. Some functions, however, are non-strict, e.g. **IF**, **AND** and **OR**. These functions may not evaluate all arguments.

16.4.3 Kinds of Programs

MUIbase knows three kinds of programs. The first one is the project program kind. In a program of this kind you can define functions and global variables. The functions can be used as trigger functions for attributes. You define a project program in the program editor (see Section 16.1 [Program editor], page 74).

The second kind is the query program kind. For this kind you can enter expressions only. An expression is allowed to contain global variables and calls to functions that are defined in the project program. However, you cannot define new global variables or functions in a query program. Query programs are entered in the query editor (see Section 14.2 [Query editor], page 53).

The third kind of programs are filter expressions. Here you can only enter expressions that contain calls to pre-defined MUIbase functions. Not all pre-defined functions are available, only those that don't have a side effect, e.g. you cannot use a function that writes data to a file. Filter expressions are entered in the change-filter dialog (see Section 10.1.2 [Changing filters], page 44).

16.4.4 Name Conventions

In a MUIbase program you can define symbols like functions and local or global variables. The names of these symbols must follow the following conventions:

- the first character of a name must be a lowercase letter. This distinguishes program symbols from table and attribute names.
- The following characters can be any letters, digits or underscore characters. Other characters like German umlauts are not allowed.

16.4.5 Accessing Record Contents

To access tables and attributes in a MUIbase program, you have to specify a path to them. A path is a dot separated list of components where each component is the name of a table or an attribute.

Paths can either be relative or absolute. Absolute paths are specified with a table name as the first component, followed by a list of attributes that lead to the final attribute you want to access. E.g. the absolute path '**Person.Name**' accesses the '**Name**' attribute in the current record of table '**Person**', or the absolute path '**Person.Father.Name**' accesses the '**Name**' attribute in the record referenced by the '**Father**' field (a reference attribute to table '**Person**').

Relative paths already have a current table to which they are relative. For example in a filter expression the current table is the table for which you write the filter expression.

The relative path for an attribute in the current table is simply the attribute name itself. For attributes that are not directly accessible from the current table but indirectly via a reference attribute, the same rules as for absolute paths apply.

It is not always clear if a specified path is a relative or an absolute one, e.g. suppose you are writing a filter expression for a table 'Foo' that has an attribute 'Bar' and there also exists a table 'Bar'. Now entering 'Bar' would be ambiguous, what is meant, the table or the attribute? Therefore all paths are first treated as relative ones. If no attribute is found for the specified path than the path is treated as global. In our example the attribute would be preferred.

But now, what if you want to access the table in the above example? Therefore the path must be given absolute. To indicate that a path is global you have to insert two colons in front of the path. In our example you would have to type '::Bar' for accessing the table.

To give you a better understanding of paths and their semantics, consider in our example that the 'Bar' attribute in the 'Foo' table is a reference to the 'Bar' table, and the 'Bar' table has an attribute 'Name'. Now you can access the 'Name' attribute by typing 'Bar.Name' or '::Bar.Name'. Both expressions have a different meaning. '::Bar.Name' means to take the current record of table 'Bar' and return the value of the 'Name' attribute of this record, whereas 'Bar.Name' takes the current record of table 'Foo', extracts the record reference of the 'Bar' field and uses this record for getting the value of the 'Name' attribute.

To make a more complete example, consider that table 'Bar' has two records. One that contains 'Ralph' and one that contains 'Steffen' in the 'Name' field. The first record should be the current one. Furthermore table 'Foo' has one record (the current one) whose 'Bar' field refers to the second record of table 'Bar'. Now '::Bar.Name' results to 'Ralph' and 'Bar.Name' to 'Steffen'.

16.4.6 Data Types for Programming

The programming language of MUIbase knows of the following data types:

Type	Description
Boolean	all expressions. Non-NIL expressions are treated as TRUE.
Integer	long integer, 32 bit, choice values are automatically converted to integers
Real	double, 64 bit
String	strings of arbitrary length
Memo	like strings but line oriented format
Date	date values
Time	time values
Record	pointer to a record

File	file descriptor for reading/writing
List	list of items, NIL is empty list.

All programming types support the NIL value.

16.4.7 Constants

The programming language of MUIbase can handle constant expressions which can be entered depending on the type of the expression:

Type	Description																						
Integer	Integer constants in the range of -2147483648 to 2147483647 can be specified as usual. Values starting with 0 are interpreted as octal numbers, values starting with 0x as hexadecimal numbers.																						
Real	Floating point constants in the range of -3.59e308 to 3.59e308 can be specified as usual, in scientific or non-scientific format. If you omit the decimal point then the number may not be treated as a real number but as an integer instead.																						
String	String constants are any character strings surrounded by double quotes, e.g. "sample string". Within the double quotes you can enter any characters except control characters or new lines. However there are special escape codes for entering such characters: <table style="margin-left: 40px;"> <tbody> <tr> <td><code>\n</code></td> <td>new line (nl)</td> </tr> <tr> <td><code>\t</code></td> <td>horizontal tabulator (ht)</td> </tr> <tr> <td><code>\v</code></td> <td>vertical tabulator (vt)</td> </tr> <tr> <td><code>\b</code></td> <td>backspace (bs)</td> </tr> <tr> <td><code>\r</code></td> <td>carriage return (cr)</td> </tr> <tr> <td><code>\f</code></td> <td>form feed (ff)</td> </tr> <tr> <td><code>\\</code></td> <td>backslash character itself</td> </tr> <tr> <td><code>\"</code></td> <td>double quote</td> </tr> <tr> <td><code>\e</code></td> <td>escape code 033</td> </tr> <tr> <td><code>\nnn</code></td> <td>character with octal code <i>nnn</i></td> </tr> <tr> <td><code>\xnn</code></td> <td>character with hex code <i>nn</i></td> </tr> </tbody> </table>	<code>\n</code>	new line (nl)	<code>\t</code>	horizontal tabulator (ht)	<code>\v</code>	vertical tabulator (vt)	<code>\b</code>	backspace (bs)	<code>\r</code>	carriage return (cr)	<code>\f</code>	form feed (ff)	<code>\\</code>	backslash character itself	<code>\"</code>	double quote	<code>\e</code>	escape code 033	<code>\nnn</code>	character with octal code <i>nnn</i>	<code>\xnn</code>	character with hex code <i>nn</i>
<code>\n</code>	new line (nl)																						
<code>\t</code>	horizontal tabulator (ht)																						
<code>\v</code>	vertical tabulator (vt)																						
<code>\b</code>	backspace (bs)																						
<code>\r</code>	carriage return (cr)																						
<code>\f</code>	form feed (ff)																						
<code>\\</code>	backslash character itself																						
<code>\"</code>	double quote																						
<code>\e</code>	escape code 033																						
<code>\nnn</code>	character with octal code <i>nnn</i>																						
<code>\xnn</code>	character with hex code <i>nn</i>																						
Memo	Same as string constants.																						
Date	Constant date values can be specified in one of the formats 'DD.MM.YYYY', 'MM/DD/YYYY', or 'YYYY-MM-DD', where 'DD', 'MM' and 'YYYY' are standing for two and four digit																						

values representing the day, month and year of the date respectively.

Time Constant time values can be entered in the format 'HH:MM:SS', where 'HH' represent the hours, 'MM' the minutes, and 'SS' the seconds.

For some other pre-defined constant values, see Section 16.25 [Pre-defined constants], page 141.

16.4.8 Command Syntax

In the remainder of this chapter, you will find the description of all commands and functions available for programming MUIbase. The following syntax is used for describing the commands:

- text written in brackets `[]` is optional. If you omit the text inside the brackets then a default value is assumed.
- text separated by a vertical bar `|` denotes several options, e.g. 'a | b' means that you can specify either 'a' or 'b'.
- text written in a font like *var* indicates a place-holder that can be filled with other expressions.
- dots `...` indicate that further expressions can follow.
- all other text is obligatory.

16.5 Defining Commands

This section lists commands for defining functions and global variables. The commands are only available for project programs.

16.5.1 DEFUN

DEFUN defines a function with the specified name, a list of arguments that are passed to the function, and a list of expressions to evaluate.

```
(DEFUN name (varlist) expr ...)
```

The name of a function must start with a lowercase character, followed by further characters, digits or underscore characters (see Section 16.4.4 [Name conventions], page 78).

The parameters *varlist* specifies the arguments of the function:

```
varlist: var1 ...
```

where *var1* ... are the names for the arguments. The names must follow the same rules as the function name.

It is also possible to add type specifiers to the arguments (see Section 16.27 [Type specifiers], page 142).

The function executes the expressions *expr*, ... one by one and returns the value of the last expression. The function may call further functions including itself. A self defined function can be called like calling a pre-defined function.

For example to count the number of elements of a list, you can define the following function:

```
(DEFUN len (l)
  (IF (= l NIL)
    0
    (+ 1 (len (REST l)))
  )
)
```

Functions defined with `DEFUN` are listed in the pop-up list-views of table and attribute dialogs (see Section 15.1.1 [Creating tables], page 59, and Section 15.2.1 [Creating attributes], page 61).

This command is only available for project programs.

See also `DEFUN*`, `DEFVAR`.

16.5.2 DEFUN*

`DEFUN*` is the star version of `DEFUN` and has the same effect as `DEFUN` (see Section 16.5.1 [DEFUN], page 81). The only difference is that functions defined with `DEFUN*` are not listed in the pop-up list-views when creating or changing tables and attributes. However, it is still possible to enter the function name in the corresponding string fields.

This command is only available for project programs.

See also `DEFUN`, `DEFVAR`.

16.5.3 DEFVAR

```
(DEFVAR var [expr])
```

Defines a global variable with initial value of *expr* or `NIL` if *expr* is missing. The name of the variables must start with a lowercase letter followed by further letters, digits or underscore characters (see Section 16.4.4 [Name conventions], page 78).

You can also add a type specifier to the variable name (see Section 16.27 [Type specifiers], page 142).

`DEFVAR` is only available for project programs. All `DEFVAR` commands should be placed on top of all function definitions.

After execution of a trigger function (when MUIbase returns to the user interface), all global variables lose their contents. They are re-initialized with their initial value *expr* on the next invocation of a trigger function. If this is not desired, use the `DEFVAR*` (see Section 16.5.4 [DEFVAR*], page 83) command which allows to store the value of global variables between program calls.

Please use global variables rarely (if at all). All global variables have to be initialized (and *expr* be evaluated if given) whenever a trigger function is called from outside.

Example: ‘`(DEFVAR x 42)`’ defines a global variable ‘`x`’ with value 42.

There are some pre-defined global variables in MUIbase (see Section 16.24 [Pre-defined variables], page 141).

See also `DEFVAR*`, `DEFUN`, `DEFUN*`, `LET`.

16.5.4 DEFVAR*

```
(DEFVAR* var [expr])
```

DEFVAR* has the same effect as the DEFVAR command (see Section 16.5.3 [DEFVAR], page 82) except that a variable defined with DEFVAR* does not lose its value after the program completes.

On the first invocation of the program, *var* is initialized with *expr* or NIL if *expr* is omitted. Subsequent calls of the program do not evaluate *expr* again but use the value of *var* from the previous call. This way it is possible to transfer information from one program call to another without storing data in an external file or a database table. Note, however, that all global variables defined with DEFVAR* lose their contents when the project program is re-compiled. If you wish to permanently store information, use a (possibly hidden) attribute in a table.

See also DEFVAR, DEFUN, DEFUN*, LET.

16.6 Program Control Functions

This section lists functions for program control, e.g. functions for defining local variables, loop functions, conditional program execution, loop control functions and more.

16.6.1 PROGN

To evaluate several expressions one by another the PROGN construction can be used.

```
(expr ...)
```

executes *expr* ... one by one. Returns the result of the last expression (or NIL if no expression has been specified). In Lisp this construct is known as (PROGN [*expr* ...]).

Example: '(1 2 3 4)' results to 4.

See also PROG1.

16.6.2 PROG1

Another way, besides the PROGN function, to evaluate several expressions one by another is the PROG1 expression.

```
(PROG1 [expr ...])
```

executes *expr* ... and returns the value of the first expression (or NIL if no expression has been specified).

Example: '(PROG1 1 2 3 4)' results to 1.

See also PROGN.

16.6.3 LET

LET defines a new block of local variables. This is useful, e.g., for defining local variables of a function. The syntax is

```
(LET (varlist) expr ...)
```

where *varlist* is a list of local variables.

```
varlist: varspec ...
```

```
varspec: (var expr) | var
```

Here *var* is the name of the variable and must start with a lowercase character, followed by further characters, digits or underscore characters (see Section 16.4.4 [Name conventions], page 78).

In the case of a (*var expr*) specification, the new variable is initialized with the given expression. In the other case the new variable is set to NIL.

It is also possible to add type specifiers to the variables. (see Section 16.27 [Type specifiers], page 142).

After initializing all variables the list of expressions *expr . . .* are evaluated and the value of the last one is returned.

For example, the following LET expression

```
(LET ((x 0) y (z (+ x 1)))
      (+ x z)
    )
```

results to 1.

See also DOTIMES, DOLIST, DO, DEFVAR.

16.6.4 SETQ

The SETQ function sets values to variables, attributes and tables.

```
(SETQ lvalue1 expr . . .)
```

Sets *lvalue1* to the value of *expr*. The dots indicate assignments for further lvalues. An lvalue is either a variable, an attribute in a table, or a table. In case of a variable, the variable must have been previously defined (e.g. by a LET expression).

Setting the value of a table means setting its program or GUI record pointer: '(SETQ *Table expr*)' sets the program record pointer of *Table* to the value of *expr*, '(SETQ *Table* expr*)' sets the GUI record pointer of it and updates the display. For more information about program and GUI record pointers, see Section 5.2 [Tables], page 18.

SETQ returns the value of the last expression.

Example: '(SETQ a 1 b 2)' assigns 1 to the variable 'a', 2 to the variable 'b' and returns 2.

See also SETQ*, LET, DEFVAR, Tables, Semantics of expressions.

16.6.5 SETQ*

SETQ* is the star version of SETQ (see Section 16.6.4 [SETQ], page 84) and has similar effects. The difference is that when assigning a value to an attribute, SETQ* calls the trigger function of that attribute (see Section 16.29.11 [Attribute trigger], page 148) instead of directly assigning the value. In case no trigger function has been specified for an attribute, SETQ* behaves like SETQ and simply assigns the value to the attribute.

Example: '(SETQ* *Table.Attr* 0)' calls the trigger function of '*Table.Attr*' with an argument of 0.

Warning: With this function it is possible to write endless loops, e.g. if you have defined a trigger function for an attribute and this function calls SETQ* to set a value to itself.

See also SETQ, LET, DEFVAR.

16.6.6 FUNCALL

FUNCALL is used to call a function with arguments.

```
(FUNCALL fun-expr [expr ...])
```

Calls the function *fun-expr* with the given arguments. The expression *fun-expr* can be any expression whose value is a pre-defined or user-defined function, e.g. a variable holding the function to call. If the number of arguments is not correct, an error message is generated.

FUNCALL returns the return value of the function call or NIL if *fun-expr* is NIL.

For more information about functional expressions, see Section 16.26 [Functional parameters], page 142.

See also APPLY.

16.6.7 APPLY

APPLY is used to apply a function to a list of arguments.

```
(APPLY fun-expr [expr ...] list-expr)
```

Applies the function *fun-expr* to a list created by `cons`'ing the arguments *expr* ... to *list-expr*. In other words: calls the function *fun-expr* with the arguments *expr* ... and *list-expr* expanded to its list elements.

The expression *fun-expr* can be any expression whose value is a pre-defined or user-defined function, e.g. a variable holding the function to call. The last argument *list-expr* must be a valid list or NIL, otherwise an error message is generated. If the number of arguments is not correct, an error occurs.

APPLY returns the return value of the function call or NIL if *fun-expr* is NIL.

For more information about functional expressions, see Section 16.26 [Functional parameters], page 142.

Example: '(APPLY + 4 (LIST 1 2 3))' returns 10.

See also FUNCALL.

16.6.8 IF

IF is a conditional operator.

```
(IF expr1 expr2 [expr3])
```

The expression *expr1* is tested. If it results to non-NIL then the value of *expr2* is returned else the value of *expr3* (or NIL if not present) is returned.

This function is not strict, that is, only one expression of *expr2* or *expr3* will be evaluated.

See also CASE, COND.

16.6.9 CASE

CASE is similar to the `switch` statement in the C language.

```
(CASE expr [case ...])
```

Here *expr* is the selection expression and *case* ... are pairs consisting of:

```
case: (value [expr ...])
```

where *value* is a single expression or a list of expressions and *expr ...* are the expressions to be executed if one of the case expression matches.

The **CASE** expression first evaluates *expr*. Then each case pair is checked whether it (or one of the expressions in the list) matches the evaluated expression. If a matching case expression is found then the corresponding expressions are executed and the value of the last expression is returned. If no case matches, **NIL** is returned.

Example: '(CASE 1 ((2 3 4) 1) (1 2))' returns 2.

See also **IF**, **COND**.

16.6.10 COND

COND is, like **IF**, a conditional operator.

```
(COND [(test-expr [expr ...]) ...])
```

COND test the first expression of each list one by one. For the first one that does not result to **NIL**, the corresponding expressions *expr ...* are evaluated and the value of the last expression is returned.

If all tested expressions result to **NIL** then **NIL** is returned.

Example

```
(COND ((> 1 2) "1 > 2")
      ((= 1 2) "1 = 2")
      ((< 1 2) "1 < 2")
      )
```

results to "1 < 2".

See also **IF**, **CASE**.

16.6.11 DOTIMES

For simple loops the **DOTIMES** command can be used.

```
(DOTIMES (name int-expr [result-expr ...]) [loop-expr ...])
```

Here *name* is the name of a new variable which will be used in the loop. The name must start with a lowercase character, followed by further characters, digits or underscore characters (see Section 16.4.4 [Name conventions], page 78).

The number of times the loop is executed is given in *int-expr*. In *result-expr ...* expressions can be specified that are executed after terminating the loop. In *loop-expr* you specify the body of the loop, that is, the expressions that are evaluated in each loop run.

Before executing the loop, **DOTIMES** computes the value of *int-expr* to determine the number of times the loop gets executed. Here *int-expr* is evaluated only once at the start of the loop and must result to an integer value. Then **DOTIMES** sets the loop variable to the values of 0 to *int-expr*-1 one by one for each loop run. First, the variable is initialized with zero and checked if it is already greater or equal to the value of *expr*. If *int-expr* is negative or **NIL** or if the variable is greater or equal to the value of *expr* then the loop is terminated and the result expressions are evaluated. Otherwise the loop expressions are evaluated and the variable is incremented by one. Then the execution returns to the termination test and, possibly, does further loop runs.

The **DOTIMES** expression returns the value of the last result expression or **NIL** if no result expression has been given.

Example

```
(DOTIMES (i 50 i) (PRINT i))
```

Prints the numbers from 0 to 49 and returns the value 50.

See also DOLIST, DO, FOR ALL, LET.

16.6.12 DOLIST

For loops through lists the DOLIST expression can be used.

```
(DOLIST (name list-expr [result-expr ...]) [loop-expr ...])
```

Here *name* is the name of a new variable which will be used in the loop. The name must start with a lowercase character, followed by further characters, digits or underscore characters (see Section 16.4.4 [Name conventions], page 78).

In *list-expr* you specify the list over which the loop should be executed, *result-expr ...* are expressions which are evaluated after terminating the loop, and *loop-expr ...* build the body of the loop.

Before executing the loop, DOLIST computes the value of *list-expr*. This expression is evaluated only once at the start of the loop and must result to a list value. Then DOTIMES sets the loop variable to the nodes of the list one by one for each loop run. First the loop variable is initialized to the first node of the list. If the list is already empty (NIL) then the loop is terminated and the result expressions are evaluated. Otherwise the loop expressions are evaluated and the variable is set to the next node of the list. Then the execution returns to the termination test and, possibly, does further loop runs.

The DOLIST expression returns the value of the last result expression or NIL if no result expression has been given.

Example

```
(DOLIST (i (SELECT * FROM Accounts)) (PRINT i))
```

Prints all records of table 'Accounts' and returns NIL.

See also DOTIMES, DO, FOR ALL, LET.

16.6.13 DO

With the DO expression arbitrary loops can be programmed.

```
(DO ([binding ...]) (term-expr [result-expr ...]) [loop-expr ...])
```

where *binding ...* are the variable bindings, each of which is either:

- a new name for a variable (which is initialized to NIL)
- a list of the form: (*name init [step]*) where *name* is a name for the new variable, *init* is the initial value of the variable, and *step* is a step expression.

Furthermore, *term-expr* is the termination test expression, *result-expr ...* are the result expressions (the default is nil) and *loop-expr ...* build the body of the loop.

The DO loop first initializes all local variables with the init expressions, then tests the termination expression. If it results to TRUE, the loop is terminated and the result expressions are evaluated. The value of the last result expression is returned. Otherwise the body of the loop (*loop-expr ...*) is executed and each variable is updated by the value of its step expression. Then the execution returns to test the terminating expression and so on.

Example

```
(DO ((i 0 (+ i 1))) ((>= i 5) i) (PRINT i))
```

Prints the values 0, 1, 2, 3 and 4 and returns the value 5. Of course this is a quite complicated way to build a simple FOR loop. Therefore a simpler version exists, the DOTIMES expression.

See also DOTIMES, DOLIST, FOR ALL, LET.

16.6.14 FOR ALL

The FOR ALL expression is used to loop over a list of records.

```
(FOR ALL table-list [WHERE where-expr] [ORDER BY order-list] DO expr ...)
```

Here *table-list* is a comma-separated list of tables, *where-expr* an expression to test each set of records, *order-list* a comma-separated list of expressions by which the record sets are ordered, and *expr ...* are the expressions that are executed for each record set.

FOR ALL first generates a list of all record sets for which the loop body should be executed. This is done like in the SELECT expression. Please see Section 16.20.12 [SELECT], page 133, for more information about how this list is generated. For each element of this list the loop body *expr ...* is executed.

For example, summing up an attribute of a table can be done in the following way:

```
(SETQ sum 0)
(FOR ALL Accounts DO
  (SETQ sum (+ sum Accounts.Amount))
)
```

The FOR ALL expression returns NIL.

See also SELECT, DOTIMES, DOLIST, DO.

16.6.15 NEXT

NEXT can be used for controlling DOTIMES, DOLIST, DO and FOR ALL loops.

Calling NEXT in the body of a loop will jump to the next loop iteration. This can be used for skipping non-interesting loop runs, like e.g. in the following example:

```
(FOR ALL Table DO
  (IF not-interested-in-the-current-record (NEXT))
  ...
)
```

See also EXIT, DOTIMES, DOLIST, DO, FOR ALL.

16.6.16 EXIT

EXIT can be used to terminate a loop.

```
(EXIT [expr ...])
```

EXIT within a loop body will terminate the loop, execute the optional expressions *expr ...*, and return the value of the last expression (or NIL in case of no expression) as the return value of the loop. Possible return expressions of the loop as for example in

```
(DOTIMES (x 10 ret-expr ...) ...)
```

are not executed.

You may use the `EXIT` function for example to end a `FOR ALL` loop when you found the record you are interested in:

```
(FOR ALL Table DO
  (IF interested-in-the-current-record (EXIT Table))
  ...
)
```

See also `NEXT`, `RETURN`, `HALT`, `DOTIMES`, `DOLIST`, `DO`, `FOR ALL`.

16.6.17 RETURN

Within a function definition you can return to the caller by using the `RETURN` command.

```
(RETURN [expr ...])
```

terminates the function, executes the optional expressions `expr ...`, and returns the value of the last expression (or `NIL` in case of no expression).

Example

```
(DEFUN find-record (name)
  (FOR ALL Table DO
    (IF (= Name name) (RETURN Table))
  )
)
```

The example searches a record whose `Name` attribute matches the given name. The function returns the first record found or `NIL` in case of no record found.

See also `HALT`, `EXIT`.

16.6.18 HALT

`HALT` can be used to terminate program execution.

```
(HALT)
```

stops program execution silently.

See also `ERROR`, `EXIT`, `RETURN`.

16.6.19 ERROR

For aborting program execution with an error message the `ERROR` function can be used.

```
(ERROR fmt [arg ...])
```

stops program execution and pops up a dialog with an error message. The error message is generated from `fmt` and the optional arguments `arg ...` like in the `SPRINTF` function (see Section 16.12.34 [`SPRINTF`], page 107).

See also `HALT`, `SPRINTF`.

16.7 Type Predicates

For each type a predicate is defined that returns `TRUE` if the supplied expression is of the specified type and `NIL` otherwise. The predicates are:

Predicate	Description
-----------	-------------

(STRP <i>expr</i>)	TRUE if <i>expr</i> is of type string, NIL otherwise.
(MEMOP <i>expr</i>)	TRUE if <i>expr</i> is of type memo, NIL otherwise.
(INTP <i>expr</i>)	TRUE if <i>expr</i> is of type integer, NIL otherwise.
(REALP <i>expr</i>)	TRUE if <i>expr</i> is of type real, NIL otherwise.
(DATEP <i>expr</i>)	TRUE if <i>expr</i> is of type date, NIL otherwise.
(TIMEP <i>expr</i>)	TRUE if <i>expr</i> is of type time, NIL otherwise.
(NULL <i>expr</i>)	TRUE if <i>expr</i> is NIL (an empty list), NIL otherwise.
(CONSP <i>expr</i>)	TRUE if <i>expr</i> is a non-empty list, NIL otherwise.
(LISTP <i>expr</i>)	TRUE if <i>expr</i> is a list (may be NIL), NIL otherwise.
(RECP <i>table expr</i>)	TRUE if <i>expr</i> is a record pointer of the given table. If <i>expr</i> is NIL then TRUE is returned (initial record). If <i>table</i> is NIL then a check is done whether <i>expr</i> is a record pointer of any table.

16.8 Type Conversion Functions

This section lists functions for converting values from one type to another one.

16.8.1 STR

STR can be used to convert an expression into a string representation.

(STR *expr*)

converts *expr* into a string representation. The type of *expr* determines the conversion:

Type	Return string
String	The string itself.
Memo	The whole memo text in one string.
Integer	String representation of integer value.
Real	String representation of real value. If <i>expr</i> is an attribute then the number decimals specified for this attribute are used, otherwise 2 decimals are used.

Choice	Label string of the choice attribute.
Date	String representation of date value.
Time	String representation of time value.
Boolean	The string "TRUE"
NIL	User defined nil string if <i>expr</i> is an attribute, the string "NIL" otherwise.
Record	String representation of record number.
Others	String representation of internal address pointer.

See also MEMO, SPRINTF.

16.8.2 MEMO

MEMO can be used to convert an expression into a memo.

(MEMO *expr*)

converts *expr* into a memo representation. It treats the expression like the STR function (see Section 16.8.1 [STR], page 90) but returns a memo text instead of a string.

See also STR.

16.8.3 INT

INT is used to convert an expression into an integer.

(INT *expr*)

converts *expr* into an integer value. Possible conversions are:

Type	Return value
String	If the complete string represents a valid integer value, it is converted into an integer. A string starting with 0 is interpreted as an octal number, one starting with 0x as hexadecimal number. Leading and following spaces are ignored. If the string does not represent an integer value, NIL is returned.
Memo	Same as for string.
Integer	The value itself.
Real	If the value lies within the integer range than the real value is rounded and returned, otherwise NIL is returned.

Choice	The internal number (starting with 0) of the current label.
Date	Number of days since 01.01.0000.
Time	Number of seconds since 00:00:00.
Record	Record number.
NIL	NIL
Others	An error message is generated and program execution is aborted.

See also REAL, ASC.

16.8.4 REAL

REAL is used to convert an expression into a value of type real.

(REAL *expr*)

converts *expr* into a real. It treats the expression like the INT function (see Section 16.8.3 [INT], page 91) but returns a value of type real instead of an integer.

See also INT.

16.8.5 DATE

DATE is used to convert an expression into a date (with your favorite friend :-).

(DATE *expr*)

converts the given expression into a date value. Possible conversions are:

Type	Return value
String	If the whole string represents a date value then the string is converted into a date value. Leading and following spaces are ignored. If it does not represent a date value, NIL is returned.
Memo	Same as for string.
Integer	A date value is generated where the given integer represents the number of days since 01.01.0000. If the integer value is too great (date value would be greater than 31.12.9999) or negative then NIL is returned.
Real	Same as for integer.
Date	The value itself.

NIL	NIL
others	An error message is generated and program execution is aborted.

See also DATEDMY.

16.8.6 TIME

TIME is used to convert an expression into a time value.

(TIME *expr*)

converts the given expression into a time value. Possible conversions are:

Type	Return value
String	If the whole string represents a time value then the string is converted into a time value. Leading and following spaces are ignored. If it does not represent a time value, NIL is returned.
Memo	Same as for string.
Integer	A time value is generated where the given integer represents the number of seconds since 00:00:00.
Real	Same as for integer.
Time	The value itself.
NIL	NIL
others	An error message is generated and program execution is aborted.

16.9 Boolean Functions

This section lists Boolean operators.

16.9.1 AND

AND checks if all of its arguments are TRUE.

(AND [*expr* ...])

checks *expr* ... one by another until one expression evaluates to NIL. If all expressions evaluate to non-NIL then the value of the last expression is returned. Otherwise NIL is returned.

This function is non-strict which means that arguments of AND may not be evaluated, e.g. in '(AND NIL (+ 1 2))' the expression '(+ 1 2)' is not evaluated since a NIL value

has already been processed, however in `'(AND (+ 1 2) NIL)'` the expression `'(+ 1 2)'` gets evaluated.

See also OR, NOT.

16.9.2 OR

OR checks if all of its arguments are NIL.

```
(OR [expr ...])
```

checks `expr ...` one by another until one expression evaluates to non-NIL. Returns the value of the first non-NIL expression or NIL if all expressions evaluate to NIL.

This function is non-strict which means that arguments of OR may not be evaluated, e.g. in `'(OR TRUE (+ 1 2))'` the expression `'(+ 1 2)'` is not evaluated since a non-NIL value (here `'TRUE'`) has already been processed, however in `'(OR (+ 1 2) TRUE)'` the expression `'(+ 1 2)'` gets evaluated.

See also AND, NOT.

16.9.3 NOT

NOT is used to invert the value of a Boolean expression.

```
(NOT expr)
```

results to TRUE if `expr` is NIL, NIL otherwise.

See also AND, OR.

16.10 Comparison Functions

In this section you will find functions for comparing values.

16.10.1 Relational Operators

For comparing two values in a MUIbase program, use

```
(op expr1 expr2)
```

where `op` is in `{=, <, <*, <*, >, >=, <=, =*, <*, >*, >=*, <=*, <=*`. The star is used for special comparison (strings are compared case insensitive, records are compared by using the order defined by the user).

The following table shows all rules for comparing two values in a MUIbase program.

Type	Order relation
Integer	<code>NIL < MIN_INT < ... < -1 < 0 < 1 < ... < MAX_INT</code>
Real	<code>NIL < -HUGE_VAL < ... < -1.0 < 0.0 < 1.0 < ... < HUGE_VAL</code>
String:	<code>NIL < "" < "Z" < "a" < "aa" < "b" < ... (case sensitive)</code> <code>NIL <* "" <* "a" <* "AA" <* "b" < ... (case insensitive)</code>
Memo:	same as string
Date	<code>NIL < 1.1.0000 < ... < 31.12.9999</code>

Time NIL < 00:00:00 < ... < 596523:14:07

Boolean NIL < TRUE

Record: NIL < any_record (records itself are not comparable with <)
 NIL <* rec1 <* rec2 (order specified by user)

See also CMP, CMP*, LIKE.

16.10.2 CMP

CMP returns an integer representing the order of its arguments.

(CMP *expr1 expr2*)

returns a value less than 0 if *expr1* is smaller than *expr2*, 0 if *expr1* is equal to *expr2*, and a value greater than 0 if *expr1* is greater than *expr2*. For determining the order the simple (non-star) order relation as for relational operators (see Section 16.10.1 [Relational operators], page 94) is used.

Do not assume that the returned value will always be -1, 0, or 1!

Example: '(CMP "Bike" "bIKE)') results to -1.

See also CMP*, Relational operators.

16.10.3 CMP*

CMP* is the star version of CMP. The difference is that CMP* uses the extended ordering as defined for relational operators (see Section 16.10.1 [Relational operators], page 94) where strings are compared case insensitive and records are compared using the user defined record order.

Example: '(CMP* "Bike" "bIKE)') results to 0.

See also CMP, Relational operators.

16.10.4 MAX

MAX returns the argument that has the largest value.

(MAX [*expr ...*])

Returns the maximum value of the arguments *expr ...*. If no arguments are given then NIL is returned. For determining the largest element the simple (non-star) order relation as for relational operators (see Section 16.10.1 [Relational operators], page 94) is used.

See also MAX*, MIN, Relational operators.

16.10.5 MAX*

MAX* is the star version of MAX. The difference is that MAX* uses the extended ordering as defined for relational operators (see Section 16.10.1 [Relational operators], page 94) where strings are compared case insensitive and records are compared using the user defined record order.

Example: '(MAX* "x" "Y)') results to "Y".

See also MAX, MIN*, Relational operators.

16.10.6 MIN

MIN returns the argument that has the smallest value.

```
(MIN [expr ...])
```

Returns the minimum value of the arguments *expr* If no arguments are given then NIL is returned. For determining the smallest element the simple (non-star) order relation as for relational operators (see Section 16.10.1 [Relational operators], page 94) is used.

See also MIN*, MAX, Relational operators.

16.10.7 MIN*

MIN* is the star version of MIN. The difference is that MIN* uses the extended ordering as defined for relational operators (see Section 16.10.1 [Relational operators], page 94) where strings are compared case insensitive and records are compared using the user defined record order.

Example: '(MIN* "x" "Y")' results to "x".

See also MIN, MAX*, Relational operators.

16.11 Mathematical Functions

Here, some mathematical functions are listed.

16.11.1 Adding Values

For adding values, use

```
(+ expr ...)
```

Returns the sum of the arguments *expr* If any argument value is NIL then the result is NIL. If the values are of type real or integer then a real (or integer) value is the result.

You may also add strings or memos. In this case the result is the concatenation of the strings/memos.

If *expr* is of type date and the rest of the arguments are integers/reals then the sum of integers/reals are interpreted as a number of days and added to *expr*. If the resulting date is out of range (smaller than 1.1.0000 or greater than 31.12.9999) then NIL is the result.

If *expr* is of type time and the rest of the arguments are integers/reals or other time values then the sum of integers/reals (interpreted as a number of seconds) and time values are added to *expr*. If the resulting time is out of range (smaller than 00:00:00 or greater than 596523:14:07) then NIL is the result.

Examples

Expression	Value
(+ 1 2 3)	6
(+ 5 1.0)	6.0
(+ "Hello" " " "world!")	"Hello world!"
(+ 28.11.1968 +365 -28 -9)	22.10.1969
(+ 07:30:00 3600)	08:30:00

(+ 03:00:00 23:59:59) 26:59:59

See also 2sub,-, 1+, 2mul,*, CONCAT, CONCAT2,ADDMONTH, ADDYEAR.

16.11.2 Subtracting Values

For subtracting values, use

`(- expr1 expr2 ...)`

Subtracts the sum of *expr2* ... from *expr1*. Here the same rules apply as for adding values (see Section 16.11.1 [add], page 96), except that strings and memos can't be subtracted.

`(- expr)` has a special meaning, it returns the negative value of *expr* (integer or real), e.g. `'(- (+ 1 2))'` results to -3.

See also 2add,+, 1-.

16.11.3 1+

1+ increases an integer or real expression by one.

`(1+ expr)`

Returns the value of *expr* (integer or real) plus one. If *expr* is NIL then NIL is returned.

See also 2add,+, 1-.

16.11.4 1-

1- decreases an integer or real expression by one.

`(1- expr)`

Returns the value of *expr* (integer or real) minus one. If *expr* is NIL then NIL is returned.

See also 2sub,-, 1+.

16.11.5 Multiplying Values

For multiplying integer/real values, use

`(* expr ...)`

Returns the multiplication of the integer/real values *expr* If all arguments are integers then an integer is returned, otherwise the result is a value of type real.

See also 2add,+, 2fdiv,/.

16.11.6 Dividing Values

For dividing integer/real values, use

`(/ expr1 [expr2 ...])`

Divides *expr1* by the multiplication of the rest of the arguments. Returns a real value. On division by zero, NIL is returned.

See also 2mul,*, DIV, MOD.

16.11.7 DIV

DIV is used for integer division.

```
(DIV int1 int2)
```

Returns the integer division of *int1* with *int2*. For example, '(DIV 5 3)' results to 1.

See also 2fdiv,/, MOD.

16.11.8 MOD

MOD is used for modulo calculation.

```
(MOD int1 int2)
```

Returns *int1* modulo *int2*. For example, '(MOD 5 3)' results to 2.

See also DIV.

16.11.9 ABS

ABS computes the absolute value of an expression.

```
(ABS expr)
```

Returns the absolute value of *expr* (integer or real). If *expr* is NIL then NIL is returned.

16.11.10 TRUNC

TRUNC truncates decimals of a real value.

```
(TRUNC real)
```

Returns the largest integer (as a real number) not greater than the specified real number. If *real* is NIL then NIL is returned.

Examples: '(TRUNC 26.1)' results to 26, '(TRUNC -1.2)' results to -2.

See also ROUND.

16.11.11 ROUND

ROUND rounds a real value.

```
(ROUND real digits)
```

Returns the specified real number rounded to *digits* decimal digits. If *real* or *digits* are NIL then NIL is returned.

Examples: '(ROUND 70.70859 2)' results to 70.71, '(ROUND 392.36 -1)' results to 390.0.

See also TRUNC.

16.11.12 RANDOM

RANDOM can be used to generate random numbers.

```
(RANDOM expr)
```

Returns a random number. On the first call the random number generator is initialized with a value generated from the current time. RANDOM generates a random number in the range of 0 . . . *expr*, excluding the value of *expr* itself. The type of *expr* (integer or real) is the return type. If *expr* is NIL then NIL is returned.

Examples:

Example	Meaning
(RANDOM 10)	returns a value from 0 to 9,
(RANDOM 10.0)	returns a value from 0.0 to 9.99999...

16.11.13 POW

POW computes the power of values.

(POW *x y*)

Returns the value of real value *x* raised to the power of real value *y*. If either *x* or *y* are NIL, or if *x* is negative and *y* not an integral number, then NIL is returned.

Example: '(POW 2 3)' results to 8.

See also SQRT, EXP.

16.11.14 SQRT

SQRT computes the square root of a number.

(SQRT *x*)

Returns the square root of real value *x*. If *x* is NIL or a negative number then NIL is returned.

See also POW.

16.11.15 EXP

EXP computes the exponential function.

(EXP *x*)

Returns the value of the base of the natural logarithm raised to the power of real value *x*. If *x* is NIL then NIL is returned.

See also POW, LOG.

16.11.16 LOG

LOG computes the natural logarithm of a number.

(LOG *x*)

Returns the natural logarithm of real value *x*. If *x* is NIL or not a positive number then NIL is returned.

See also EXP.

16.12 String Functions

This section deals with functions useful for strings.

16.12.1 LEN

LEN computes the length of a string.

(LEN *str*)

Returns the length of the given string or NIL if *str* is NIL.

See also WORDS, LINES, MAXLEN.

16.12.2 LEFTSTR

LEFTSTR extracts a sub string out of a string.

(LEFTSTR *str len*)

Returns the left part of the given string with at most *len* characters. If *str* or *len* are NIL or if *len* is negative then NIL is returned.

Example: '(LEFTSTR "Hello world!" 5)' results to "Hello".

See also RIGHTSTR, MIDSTR, WORD, LINE.

16.12.3 RIGHTSTR

RIGHTSTR extracts a sub string out of a string.

(RIGHTSTR *str len*)

Returns the right part of the given string with at most *len* characters. If *str* or *len* are NIL or if *len* is negative then NIL is returned.

Example: '(RIGHTSTR "Hello world!" 6)' results to "world!".

See also LEFTSTR, MIDSTR, WORD, LINE.

16.12.4 MIDSTR

MIDSTR extracts a sub string out of a string.

(MIDSTR *str pos len*)

Returns a part of the given string with at most *len* characters. The sub string starts at the *pos*-th position (starting with zero). If *len* is NIL then the full sub string starting at *pos* is returned. If *str* is NIL or if *len* is negative then NIL is returned. If *pos* is out of range, that is, negative or greater than the string length, NIL is returned.

Example: '(MIDSTR "Hello world!" 3 5)' results to "lo wo".

See also LEFTSTR, RIGHTSTR, WORD, LINE, SETMIDSTR, INSMIDSTR.

16.12.5 SETMIDSTR

SETMIDSTR replaces a sub string in a string.

(SETMIDSTR *str index set*)

Returns a copy of string *str* where the sub string starting at *index* is overwritten with string *set*. The length of the returned string is greater or equal to the length of *str*. If one of the arguments is NIL or if *index* is out of range then NIL is returned.

Example: '(SETMIDSTR "Hello world!" 6 "Melanie!)"' results to "Hello Melanie!".

See also INSMIDSTR, REPLACESTR.

16.12.6 INSMIDSTR

INSMIDSTR is used to insert a sub string into a string.

```
(INSMIDSTR str index insert)
```

Returns a copy of string *str* where the string *insert* has been inserted at the given index. If one of the arguments is NIL or if *index* is out of range then NIL is returned.

Example: `'(INSMIDSTR "Hello world!" 6 "MUIbase-")'` results to "Hello MUIbase-world!".

See also SETMIDSTR, REPLACESTR.

16.12.7 INDEXSTR

INDEXSTR searches a string for the first occurrence of a sub string.

```
(INDEXSTR str substr)
```

Searches for the first occurrence of *substr* in *str*. String comparison is done case-sensitive. Returns the index (starting with 0) of the sub string in *str* or NIL if the sub string is not present. If one of the arguments is NIL then NIL is returned.

Example: `'(INDEXSTR "Hello world!" "world")'` returns 6.

See also INDEXSTR*, RINDEXSTR, RINDEXSTR*, INDEXBRK, INDEXBRK*.

16.12.8 INDEXSTR*

INDEXSTR* has the same effect as INDEXSTR (see Section 16.12.7 [INDEXSTR], page 101) except that string comparison is done case-insensitive.

See also INDEXSTR, RINDEXSTR, RINDEXSTR*, INDEXBRK, INDEXBRK*.

16.12.9 INDEXBRK

INDEXBRK searches for the first occurrence of a character in a string.

```
(INDEXBRK str brkstr)
```

Searches for the first occurrence of a character from *brkstr* in *str*. String comparison is done case-sensitive. Returns the index (starting with 0) of the first character found in *str* or NIL if no character is found. If one of the arguments is NIL then NIL is returned.

Example: `'(INDEXBRK "Hello world!" "aeiou")'` returns 1.

See also INDEXBRK*, RINDEXBRK, RINDEXBRK*, INDEXSTR, INDEXSTR*.

16.12.10 INDEXBRK*

INDEXBRK* has the same effect as INDEXBRK (see Section 16.12.9 [INDEXBRK], page 101) except that string comparison is done case-insensitive.

See also INDEXBRK, RINDEXBRK, RINDEXBRK*, INDEXSTR, INDEXSTR*.

16.12.11 RINDEXSTR

RINDEXSTR searches a string for the last occurrence of a sub string.

```
(RINDEXSTR str substr)
```

Searches for the last occurrence of *substr* in *str*. String comparison is done case-sensitive. Returns the index (starting with 0) of the sub string in *str* or NIL if the sub string is not present. If one of the arguments is NIL then NIL is returned.

Example: `'(RINDEXSTR "Do itashimashite." "shi")'` returns 11.

See also `RINDEXSTR*`, `INDEXSTR`, `INDEXSTR*`, `RINDEXBRK`, `RINDEXBRK*`.

16.12.12 RINDEXSTR*

`RINDEXSTR*` has the same effect as `RINDEXSTR` (see Section 16.12.11 [`RINDEXSTR`], page 101) except that string comparison is done case-insensitive.

See also `RINDEXSTR`, `INDEXSTR`, `INDEXSTR*`, `RINDEXBRK`, `RINDEXBRK*`.

16.12.13 RINDEXBRK

`RINDEXBRK` searches for the last occurrence of a character in a string.

`(RINDEXBRK str brkstr)`

Searches for the last occurrence of a character from *brkstr* in *str*. String comparison is done case-sensitive. Returns the index (starting with 0) of the last character found in *str* or `NIL` if no character is found. If one of the arguments is `NIL` then `NIL` is returned.

Example: `'(RINDEXBRK "Konnichiwa" "chk")'` returns 6.

See also `RINDEXBRK*`, `INDEXBRK`, `INDEXBRK*`, `RINDEXSTR`, `RINDEXSTR*`.

16.12.14 RINDEXBRK*

`RINDEXBRK*` has the same effect as `RINDEXBRK` (see Section 16.12.13 [`RINDEXBRK`], page 102) except that string comparison is done case-insensitive.

See also `RINDEXBRK`, `INDEXBRK`, `INDEXBRK*`, `RINDEXSTR`, `RINDEXSTR*`.

16.12.15 REPLACESTR

`REPLACESTR` replaces sub strings by other strings.

`(REPLACESTR str [substr1 replacestr1 ...])`

Replaces all occurrences of *substr1* in *str* by *replacestr1*. Continues replacing further sub strings in the new string using the next pair of search and replacement string until all arguments have been processed. Note that the number of arguments must be odd with arguments at even positions specifying the search strings each followed by the replacement string. Due to the fact that the result of a replacement is used in the next following replacement, multiple replacements can take place. This should be considered when using this function. A different order of the arguments might help resolving conflicts since replacements are done from left to right.

If any of the strings are `NIL` or any search string is empty then `NIL` is returned.

Example: `'(REPLACESTR "black is white" "black" "white" "white" "black")'` results to "black is black".

See also `REPLACESTR*`, `SETMIDSTR`, `INSMIDSTR`, `REMCHARS`.

16.12.16 REPLACESTR*

`REPLACESTR*` has the same effect as `REPLACESTR` (see Section 16.12.15 [`REPLACESTR`], page 102) except that string comparison is done case-insensitive for searching sub strings.

See also `REPLACESTR`, `SETMIDSTR`, `INSMIDSTR`, `REMCHARS`.

16.12.17 REMCHARS

REMCHARS removes characters from a string.

(REMCHARS *str chars-to-remove*)

Returns a copy of *str* where all characters of *chars-to-remove* are removed from. If *str* or *chars-to-remove* are NIL then NIL is returned.

Example: '(REMCHARS *your-string* " \t\n")' removes all spaces, tabs and newline characters from *your-string*.

See also REPLACESTR, TRIMSTR.

16.12.18 TRIMSTR

TRIMSTR removes leading and trailing characters from a string.

(TRIMSTR *str [front back]*)

Returns a copy of *str* where leading and trailing characters have been removed. If called with one argument only, spaces, form-feeds, newlines, carriage returns, and horizontal and vertical tabs are removed. When called with three arguments, *front* specifies the leading and *back* specifies the trailing characters to be removed. Note that TRIMSTR cannot be called with two arguments.

If any of *str*, *front*, or *back* is NIL then NIL is returned.

Example: (TRIMSTR " I wrecked Selma's bike. ") results to "I wrecked Selma's bike.", (TRIMSTR "007 " "0" " \f\n\r\t\v") results to "7".

See also REMCHARS.

16.12.19 WORD

WORD returns a word of a string.

(WORD *str num*)

Returns the *num*-th word (starting with zero) of the given string. Words in a string are non-empty sub strings separated by one or more non-breakable space characters (e.g. space, tab or newline characters).

If *str* or *num* are NIL, or if *num* is out of range, that is, less than zero or greater or equal to the number of words, then NIL is returned.

Example: '(WORD "Therefore, I lend Selma my bike." 3)' results to "Selma".

See also WORDS, LINE, FIELD, LEFTSTR, RIGHTSTR, MIDSTR, STRTOLIST.

16.12.20 WORDS

WORDS counts the number of words in a string.

(WORDS *str*)

Returns the number of words of the given string or NIL if *str* is NIL. Words are sub strings separated by one or more non-breakable space characters (e.g. space, tab, or newline characters).

Example: '(WORDS "Actually, it wasn't really my bike.")' results to 6.

See also WORD, FIELDS, LINES, LEN.

16.12.21 FIELD

FIELD returns a field in a string.

```
(FIELD str num [sep [quotes]])
```

Returns the *num*-th field (starting with zero) of the given string. Fields in a string are sub strings separated by exactly one separator character. A field may be an empty string. Argument *sep* contains the characters that separate fields. If *sep* is NIL or not provided then non-breakable space characters (e.g. space, tab, or newline characters) are used. If *quotes* is given and not NIL then fields can be surrounded by double quotes and may contain separator characters. The double quotes are stripped when returning the field.

If *str* or *num* are NIL, or if *num* is out of range, that is, less than zero or greater or equal to the number of fields, then NIL is returned.

Example: ‘(FIELD "My name is \"Darth Vader\"" 3 " " TRUE)’ results to "Darth Vader".

See also FIELDS, WORD, LEFTSTR, RIGHTSTR, MIDSTR, STRTOLIST.

16.12.22 FIELDS

FIELDS counts the number of fields in a string.

```
(FIELDS str [sep [quotes]])
```

Returns the number of fields in the given string or NIL if *str* is NIL. Fields in a string are sub strings separated by exactly one separator character. A field may be an empty string. Argument *sep* contains the characters that separate fields. If *sep* is NIL or not provided then non-breakable space characters (e.g. space, tab, or newline characters) are used. If *quotes* is given and not NIL then fields can be surrounded by double quotes and may contain separator characters.

See also FIELD, WORDS, LEN.

16.12.23 STRTOLIST

STRTOLIST converts a string to a list of sub-strings.

```
(STRTOLIST str [sep])
```

Creates a list of sub-strings by breaking the string *str* at the occurrences of the separation sequence *sep*. If *sep* is not specified then the tab character "\t" is used. If *sep* is the empty string "" then a list of all characters in the string is returned.

If *str* or *sep* are NIL then NIL is returned.

Examples

‘(STRTOLIST "I\tlike\tJapan.")’ results to ("I" "like" "Japan.").

‘(STRTOLIST "Name|Street|City" "|")’ results to ("Name" "Street" "City").

‘(STRTOLIST "abc" "")’ results to ("a" "b" "c").

See also MEMOTOLIST, LISTTOSTR, WORD.

16.12.24 LISTTOSTR

LISTTOSTR converts a list of items into a string.

```
(LISTTOSTR list [sep])
```

Converts the given list of items into a string by concatenation of the string representations of each list element separated by the sequence *sep*. If *sep* is not specified then the tab character "\t" is used. If *list* or *sep* are NIL then NIL is returned.

Examples

‘(LISTTOSTR (LIST "Peter is" 18 "years old"))’ results to: "Peter is\t18\tyears old".

‘(LISTTOSTR (LIST "Name" "Street" "City") "|")’ results to: "Name|Street|City".

See also LISTTOMEMO, CONCAT, CONCAT2, STRTOLIST.

16.12.25 CONCAT

CONCAT concatenates strings.

```
(CONCAT [str ...])
```

Returns the concatenation of the given list of strings where space characters have been inserted between the strings. If one of the strings is NIL, or the list is empty, then NIL is returned.

Example: ‘(CONCAT "I" "thought" "it" "was" "an" "abandoned" "bike.")’ results to "I thought it was an abandoned bike."

See also CONCAT2, 2add,+, LISTTOSTR, COPYSTR, SPRINTF.

16.12.26 CONCAT2

CONCAT2 concatenates strings.

```
(CONCAT2 insert [str ...])
```

Returns the concatenation of the given list of strings. The strings will be separated with the given *insert* string. If *insert* is NIL, one of the strings is NIL, or the list is empty, then NIL is returned.

Example: ‘(CONCAT2 "! " "But" "it" "wasn't!")’ results to "But! it! wasn't!".

See also CONCAT, 2add,+, LISTTOSTR, COPYSTR, SPRINTF.

16.12.27 COPYSTR

COPYSTR creates copies of a string.

```
(COPYSTR str num)
```

Returns a string consisting of *num* times the string *str*. If *str* is NIL, *num* is NIL or less than zero, NIL is returned.

Example: ‘(COPYSTR "+-" 5)’ results to "+-+-+-+-.".

See also CONCAT, CONCAT2, 2add,+, SPRINTF.

16.12.28 SHA1SUM

SHA1SUM computes the SHA1 hash of a string.

(SHA1SUM *str*)

Returns a string containing the SHA1 hash of the given string. If *str* is NIL then NIL is returned.

Example: '(SHA1SUM "flower, sun and beach")' results to "47b6c496493c512b40e042337c128d85ecf15ba4"

See also ADMINPASSWORD, demo Users.mb.

16.12.29 UPPER

UPPER converts a string to upper case.

(UPPER *str*)

Returns a copy of the given string where all characters are converted to upper case. If *str* is NIL then NIL is returned.

Example: '(UPPER "Selma found a letter attached to my bike.")' results to "SELMA FOUND A LETTER ATTACHED TO MY BIKE.".

See also LOWER.

16.12.30 LOWER

LOWER converts a string to lower case.

(LOWER *str*)

Returns a copy of the given string where all characters are converted to lower case. If *str* is NIL then NIL is returned.

Example: '(LOWER "The letter was from Silke.")' results to "the letter was from silke.".

See also UPPER.

16.12.31 ASC

ASC converts a character to its internal integer representation.

(ASC *str*)

Returns the internal integer code of the first character of *str*. On Windows, Mac OS and Linux this is the unicode representation. On Amiga, it is the 8-bit integer code in the default character encoding. If *str* is empty, 0 is returned. If *str* is NIL, NIL is returned.

Example: (ASC "A") results to 65.

See also CHR, INT.

16.12.32 CHR

CHR converts an integer code to a character.

(CHR *int*)

Returns a string containing the character with integer code *int*. On Windows, Mac OS and Linux, *int* is interpreted as a unicode character. On Amiga, *int* is the 8-bit integer in the default character encoding. If *int* is 0, an empty string is returned. If *int* is NIL or not in the range of valid character values, NIL is returned.

Example: `'(CHR 67)'` results to `"C"`.

See also `ASC`, `STR`.

16.12.33 LIKE

`LIKE` compares strings.

`(LIKE str1 str2)`

Returns `TRUE` if *str1* matches *str2*, `NIL` otherwise. The string *str2* may contain the joker characters `'?`' and `'*'` where `'?`' matches exactly one character and `'*'` matches a string of any length. String comparison is done case insensitive.

Example: `'(LIKE "Silke has been in France for one year." "*France*")'` results to `TRUE`.

See also Comparison functions.

16.12.34 SPRINTF

`SPRINTF` formats a string with various data.

`(SPRINTF fmt [expr ...])`

`SPRINTF` takes a series of arguments, converts them to strings, and returns the formatted information as one string. The string *fmt* determines exactly what gets written to the return string and may contain two types of items: ordinary characters which are always copied verbatim and conversion specifiers which direct `SPRINTF` to take arguments from its argument list and format them. Conversion specifiers always begin with a `'%'` character.

Conversion specifiers always take the following form:

`[%flags] [width] [.precision] type`

where

- The optional *flags* field controls output justification, sign character on numerical values, decimal points, and trailing blanks.
- The optional *width* field specifies the minimum number of characters to print (the field width), with padding done with blanks or zeros.
- The optional *precision* field specifies either the maximum number of characters to be printed for types string, Boolean, date and time, or the number of digits after the decimal point to be printed for values of type real.
- The *type* field specifies the actual type of the argument that `SPRINTF` will be converting, such as string, integer, real, etc.

Note that all of the above fields are optional except for *type*. The following tables list the valid options for these fields.

Flags field

- : The result is left justified, with padding done on the right using blanks. By default when `'-'` is not specified, the result is right justified with padding on the left with `'0'`'s or blanks.
- +: The result will always have a `'-'` or `'+'` character prepended to it if it is a numeric conversion.

- 0: For numbers padding on the left is done using leading zeros instead of spaces.
- space*: Positive numbers begin with a space instead of a '+' character, but negative values still have a prepended '-'.

Width field

- n*: A minimum of *n* characters are output. If the conversion has less than *n* characters, the field is padded with blanks or leading zeros.
- *: The width specifier is supplied in the argument list as an integer or real value, before the actual conversion argument. This value is limited to the range of 0 to 999.

Precision field

- .n*: For string, Boolean, date and time values, *n* is the maximum number of characters written from the converted item. For conversions of real values, *n* specifies the number of digits after the decimal point (conversions 'f' and 'e') or the number of significant digits (conversion 'g'). For integer conversions this field is ignored.
- .**: The precision is supplied in the argument list as an integer or real value, before the actual conversion argument. This value is limited to the range of 0 to 999.

Type field

- b*: Converts a Boolean parameter to "TRUE" or "NIL".
- i*: Converts an integer value to a signed decimal notation.
- o*: Converts an integer value to an unsigned octal notation.
- x*: Converts an integer value to an unsigned hexadecimal notation using lowercase letters 'abcdef'.
- X*: Converts an integer value to an unsigned hexadecimal notation using uppercase letters 'ABCDEF'.
- e*: Converts a real number using the format [-]d.ddde+dd. Exactly one digit is before the decimal point, followed by an 'e', followed by an exponent. The number of digits after the decimal point is determined by the precision field, or is 2 if precision is not specified. The decimal point will not appear if precision is 0.
- f*: Converts a real value using the format [-]ddd.ddd. The number of digits after the decimal point is determined by the precision field, or is 2 if precision is not specified. The decimal point will not appear if precision is 0.
- g*: Converts a real value using style 'e' or 'f' depending on the number of digits for representing the value. If the precision is not specified then 15 significant digits are used. Trailing zeros other than a single zero after the decimal point are removed.
- s*: Writes a string value until either the end of string is reached or the number of characters written equals the precision field.

- d: Converts a date value.
 t: Converts a time value.
 %: The character '%' is written, and no argument is converted.

SPRINTF returns the formatted string or NIL in case *fmt* is NIL.

Examples

Call	Result
(SPRINTF "Hello")	"Hello"
(SPRINTF "%s" "Hello")	"Hello"
(SPRINTF "%10s" "Hello")	" Hello"
(SPRINTF "%-10.10s" "Hello")	"Hello "
(SPRINTF "%010.3s" "Hello")	" Hel"
(SPRINTF "%-5.3b" TRUE)	"TRU "
(SPRINTF "%i" 3)	"3"
(SPRINTF "%03i" 3)	"003"
(SPRINTF "%0- 5.3i" 3)	" 3 "
(SPRINTF "%f" 12)	"12.00"
(SPRINTF "%10e" 12.0)	" 1.20e+01"
(SPRINTF "%+-10.4f" 12.0)	"+12.0000 "
(SPRINTF "%10.5t" 12:30:00)	" 12:30"
(SPRINTF "%d" 28.11.1968)	"28.11.1968"
(SPRINTF "He%s %5.5s!" "llo" "world champion ship")	"Hello world!"

See also PRINTF, FPRINTF, STR, 2add,+,CONCAT, CONCAT2, COPYSTR.

16.13 Memo Functions

This section deals with functions useful for memos.

16.13.1 LINE

LINE extracts a line in a memo.

(LINE *memo num*)

Returns the *num*-th line (starting with zero) of the given memo. The line string will not have a terminating newline character. If *memo* or *num* are NIL or if *num* is out of range, that is, less than zero or greater or equal to the number of lines, then NIL is returned.

See also LINES, WORD.

16.13.2 LINES

LINES returns the number of lines in a memo.

(LINES *memo*)

Returns the number of lines of the given memo or NIL if *memo* is NIL.

See also LINE, WORDS, LEN.

16.13.3 MEMOTOLIST

MEMOTOLIST converts a memo into a list of strings.

```
(MEMOTOLIST memo [expandstr])
```

Converts the given memo to a list. If *memo* is NIL then NIL is returned, otherwise a list is generated where each element contains one line of the memo.

If *expandstr* is given and is not NIL then resulting list of strings is further processed by applying STRTOLIST to each list element. This results into a list of lists of strings.

Examples

‘(MEMOTOLIST "My insurance\npays for\nthe wrecked bike.")’ results to ("My insurance" "pays for" "the wrecked bike.").

‘(MEMOTOLIST "Here is\ta multi-columned\nexample." TRUE)’ results to (("Here is" "a multi-columned") ("example")).

See also STRTOLIST, LISTTOMEMO.

16.13.4 LISTTOMEMO

LISTTOMEMO converts a list into a memo.

```
(LISTTOMEMO list)
```

Converts the given list into a memo. If *list* is NIL then NIL is returned, otherwise a memo is generated where each line consists of the string representation of the corresponding list element. If a list element is a sub-list then LISTTOSTR (see Section 16.12.24 [LISTTOSTR], page 105) is applied on it before integrating the resulting string into the memo.

Examples

‘(LISTTOMEMO (LIST "Silke" "lends me" "'my' bike" "till" 01.09.1998))’ results to: "Silke\nlends me\n'my' bike\ntill\n01.09.1998".

‘(LISTTOMEMO (LIST (LIST "Name" "Birthday") (LIST "Steffen" 28.11.1968)))’ results to: "Name\tBirthday\nSteffen\t28.11.1968".

See also LISTTOSTR, MEMOTOLIST.

16.13.5 FILLMEMO

FILLMEMO fills in a memo with the results of expressions.

```
(FILLMEMO memo)
```

Creates a copy of the given memo where all substrings of the form ‘\$(*expr*)’ are replaced by their results after evaluation.

Example: ‘(FILLMEMO "(+ 1 1) is \$(+ 1 1).")’ results to "(+ 1 1) is 2."

Please use only small expressions in the memo as debugging and tracking down errors is not easy here.

See also FORMATMEMO, INDENTMEMO.

16.13.6 FORMATMEMO

FORMATMEMO formats a memo.

(FORMATMEMO *memo width [fill [singlelinesec]]*)

Formats *memo* to a memo with lines not longer than *width* characters. If *fill* is given and non-NIL then spaces are used to pad the lines to exactly *width* characters. The memo is processed section-wise. A section starts at the first non-white-space character. If *singlelinesec* is specified and non-NIL then all characters until the end of this line are taken as the section. Otherwise, all characters on this and the following lines are counted as the section until a line starting with a white-space character is reached. The whole section is formatted word-wise, that is, as many words are put on one line as there are space for. Remaining words are then put on the next line and so on.

See also FILLMEMO, INDENTMEMO.

16.13.7 INDENTMEMO

INDENTMEMO indents a memo by putting spaces to the left.

(INDENTMEMO *memo indent*)

Returns a copy of the given memo where each line is indented by *indent* space characters. If *memo* or *indent* is NIL then NIL is returned. If *indent* is negative, a value of 0 is used.

See also FILLMEMO, FORMATMEMO.

16.14 Date and Time Functions

This section deals with functions useful for date and time values.

16.14.1 DAY

DAY extracts the day field of a date.

(DAY *date*)

Returns an integer representing the day of the given date value. If *date* is NIL then NIL is returned.

See also MONTH, YEAR, DATEDMY.

16.14.2 MONTH

MONTH extracts the month field of a date.

(MONTH *date*)

Returns an integer representing the month of the given date value. If *date* is NIL then NIL is returned.

See also DAY, YEAR, DATEDMY, MONTHDAYS.

16.14.3 YEAR

YEAR extracts the year field of a date.

(YEAR *date*)

Returns an integer representing the year of the given date value. If *date* is NIL then NIL is returned.

See also DAY, MONTH, DATEDMY, YEARDAYS.

16.14.4 DATEDMY

DATEDMY creates a date value from day, month, and year.

(DATEDMY *day month year*)

Creates a date value from the given day, month, and year. If any of *day*, *month*, or *year* is NIL or out of the valid range, or if the resulting date is invalid, then NIL is returned.

Example: '(DATEDMY 28 11 1968)' results to the 28th of November, 1968.

See also DATE, TODAY, DAY, MONTH, YEAR.

16.14.5 MONTHDAYS

MONTHDAYS gets the number of days of a month.

(MONTHDAYS *month year*)

Returns the number of days of the given month and year as an integer. If *month* is NIL or out of the valid range (less than 1 or greater than 12) then NIL is returned. If *year* is NIL then a non-leap year is considered for computing the number of days. If *year* is invalid (less than 0 or greater than 9999) then NIL is returned.

Examples: '(MONTHDAYS 2 2004)' results to 29, '(MONTHDAYS 2 NIL)' results to 28.

See also YEARDAYS, MONTH.

16.14.6 YEARDAYS

YEARDAYS gets the number of days of a year.

(YEARDAYS *year*)

Returns the number of days of the given year as an integer. If *year* is NIL or out of the valid range (less than 0 or greater than 9999) then NIL is returned.

Examples: '(YEARDAYS 2004)' results to 366, '(YEARDAYS 2005)' results to 365.

See also MONTHDAYS, YEAR.

16.14.7 ADDMONTH

ADDMONTH adds a number of months to a date.

(ADDMONTH *date months*)

Returns a date value where the given number of months has been added to the given date value. Negative values for *months* subtract months. If *date* or *months* is NIL, or the resulting date is invalid, then NIL is returned.

ADDMONTH handles over- and underflow of the month field by adjusting the year field accordingly. In case the day field exceeds the maximum number of days of the resulting month, it is decremented to the maximum allowed day.

Examples: '(ADDMONTH 30.01.2004 1)' results to 29.02.2004, '(ADDMONTH 30.01.2004 -1)' results to 30.12.2003.

See also ADDYEAR, 2add,+.

16.14.8 ADDYEAR

ADDEAR adds a number of years to a date.

(ADDEAR *date years*)

Returns a date value where the given number of years has been added to the given date value. Negative values for years subtract years. If *date* or *years* is NIL, or the resulting date is invalid, then NIL is returned.

ADDEAR decrements the day field by 1 in case *date* represents February 29th and the resulting year is not a leap year.

Examples: '(ADDEAR 29.02.2004 1)' results to 28.02.2005, '(ADDMONTH 04.02.2004 -1962)' results to 04.02.0042.

See also ADDMONTH, 2add,+.

16.14.9 TODAY

TODAY returns the current date.

(TODAY)

Returns the current date as a date value.

See also NOW, DATEDMY.

16.14.10 NOW

NOW returns the current time.

(NOW)

Returns the current time as a time value.

See also TODAY.

16.15 List Functions

This section lists functions for processing lists.

16.15.1 CONS

CONS builds a pair of expressions.

(CONS *elem list*)

Constructs a new list. The first element of the new list is *elem*, the rest are the elements of *list* (which should be a list or NIL). The list *list* is not copied, only a pointer is used to reference it!

Example: '(CONS 1 (CONS 2 NIL))' results to (1 2).

The elements of a list can be of any type, e.g. it's also possible to have a list of lists (e.g. see Section 16.20.12 [SELECT], page 133). The CONS constructor can also be used to build pairs of elements, e.g. '(CONS 1 2)' is the pair with the two integers 1 and 2.

See also LIST, FIRST, REST.

16.15.2 LIST

LIST generates a list out of its arguments.

```
(LIST [elem ...])
```

takes the arguments *elem* ... and generates a list of it. This is equivalent to calling (CONS *elem* (CONS ... NIL)). Note that NIL alone stands for an empty list.

See also CONS, LENGTH.

16.15.3 LENGTH

LENGTH determines the length of a list.

```
(LENGTH list)
```

returns the length of the given list.

Example: '(LENGTH (LIST "a" 2 42 3))' results to 4.

See also LIST.

16.15.4 FIRST

FIRST extracts the first element in a list.

```
(FIRST list)
```

returns the first element of the given list. If *list* is empty (NIL) then NIL is returned.

See also REST, LAST, NTH, CONS.

16.15.5 REST

REST returns the sub-list after the first element of a list.

```
(REST list)
```

returns the rest of the given list (the list without the first element). If *list* is empty (NIL) then NIL is returned.

Example: '(REST (LIST 1 2 3))' results to (2 3).

See also FIRST, CONS.

16.15.6 LAST

LAST extracts the last element in a list.

```
(LAST list)
```

Returns the last element of the given list or NIL if *list* is NIL.

See also FIRST, NTH.

16.15.7 NTH

NTH extracts the n-th element of a list.

```
(NTH n list)
```

Returns the *n*-th element of the given list (starting with 0) or NIL if the element doesn't exist.

See also FIRST, LAST.

16.15.8 APPEND

APPEND concatenates lists.

```
(APPEND [list ...])
```

returns the concatenation of *list*

Example: '(APPEND (list 1 2) (list 3 4) (list 5))' results to (1 2 3 4 5).

See also LIST.

16.15.9 REVERSE

REVERSE reverses a list.

```
(REVERSE list)
```

returns the reverse list.

Example: '(REVERSE (list 1 2 3))' results to (3 2 1).

16.15.10 MAPFIRST

MAPFIRST applies a function to all list elements.

```
(MAPFIRST func list [...])
```

Builds a list whose elements are the result of the specified function called with the arguments of the given list elements one by one. The length of the returned list is as long as the length of the longest specified list. If one of the specified lists is too short then the list is padded with NIL elements.

Examples

Expression	Value
(MAPFIRST 1+ (LIST 1 2 3))	(2 3 4)
(MAPFIRST + (LIST 1 2 3) (LIST 2 3))	(3 5 NIL)

16.15.11 SORTLIST

SORTLIST sorts the elements of a list.

```
(SORTLIST func list)
```

Returns a copy of the specified list that has been sorted using the function *func* for ordering. The order function must take two arguments one for each element and return an integer value less than zero if the first element is smaller than the second one, a value greater than zero if the first element is greater than the second one, and a value of zero if the two elements are equal.

Example for a string comparing function usable for sorting:

```
(DEFUN cmp_str (x y)
  (COND
    ((< x y) -1)
    (> x y) 1)
  (TRUE 0)
```

```
)
)
```

Now you can sort a list by calling:

```
(SORTLIST cmp_str (LIST "hi" "fine" "great" "ok"))
```

which results to ("fine" "great" "hi" "ok").

See also SORTLISTGT, MAPFIRST.

16.15.12 SORTLISTGT

SORTLIST sorts the elements of a list.

```
(SORTLISTGT gtfunc list)
```

Like SORTLIST but here you specify an order function that returns a value not equal to NIL if the first element is greater then the second one, and NIL otherwise.

Example: ‘(SORTLISTGT > (LIST "hi" "fine" "great" "ok"))’ result to ("fine" "great" "hi" "ok").

See also SORTLIST, MAPFIRST.

16.16 Input Requesting Functions

For requesting information from the user, the following functions can be used.

16.16.1 ASKFILE

ASKFILE prompts the user for entering a filename.

```
(ASKFILE title oktext default savemode)
```

Pops up a file dialog for entering a filename. The window title can be set in *title*, the text of the ‘Ok’ button in *oktext*, and the initial filename in *default*. You may specify NIL for one of them to use default values. The last argument *savemode* (Boolean) allows setting the file dialog to a save mode. This mode should be used when asking for a filename to write something to.

ASKFILE returns the entered filename as string or NIL in case the user canceled the dialog.

See also ASKDIR, ASKSTR.

16.16.2 ASKDIR

ASKDIR prompts the user for entering a directory name.

```
(ASKDIR title oktext default savemode)
```

Pops up a file dialog for entering a directory name. The arguments are used in the same way as in ASKFILE (see Section 16.16.1 [ASKFILE], page 116).

ASKDIR returns the entered directory name as string or NIL in case the user canceled the dialog.

See also ASKFILE, ASKSTR.

16.16.3 ASKSTR

ASKSTR prompts the user for entering a string.

```
(ASKSTR title oktext default maxlen [secret])
```

Pops up a dialog asking for a string to enter. The window title, the text of the ‘Ok’ button, and the initial value can be set in *title*, *oktext*, and *default* respectively (strings or NIL for default values), *maxlen* determines the maximum characters the user can enter. If *secret* is given and is not NIL then the entered string is made invisible by displaying a bullet sign for each string character.

ASKSTR returns the entered string or NIL in case the user canceled.

See also ASKFILE, ASKDIR, ASKCHOICESTR, ASKINT.

16.16.4 ASKINT

ASKINT prompts the user for entering an integer value.

```
(ASKINT title oktext default min max)
```

Pops up a dialog asking for an integer to enter. The window title and the text of the ‘Ok’ button can be specified in *title* and *oktext* (strings or NIL for default values). In *default* you pass the initial integer value or NIL to start with an empty editing field. In *min* and *max* you can set the integer range. Entered values outside this range are not accepted by the dialog. Use NIL for default min and max values.

ASKINT returns the entered integer or NIL if the user canceled the dialog.

See also ASKSTR.

16.16.5 ASKCHOICE

ASKCHOICE prompts the user to select one item out of many items.

```
(ASKCHOICE title oktext choices default [titles])
```

Pops up a dialog allowing the user to choose one item out of a list of items. You can set the window title and the text of the ‘Ok’ button in *title* and *oktext* (strings or NIL for default values). In *choices* you specify a list of choices. You can use a multi-column format by providing each choice item as a list of sub-items. The initial choice value can be set in *default* and is the index in the list of choices (starting with index 0 for the first item). Use NIL for no initial choice. If the optional argument *titles* is specified and is non-NIL then a list header containing *titles* is shown. For using a multi-column format, specify *titles* as a list of column titles.

Both, *choices* and *titles*, can also be given as a memo and a string (instead of lists). If so, they are converted to lists automatically by calling (MEMOTOLIST *choices* TRUE) (see Section 16.13.3 [MEMOTOLIST], page 110) and (STRTOLIST *titles*) (see Section 16.12.23 [STRTOLIST], page 104) respectively.

ASKCHOICE returns the index of the chosen item or NIL if the user canceled the dialog.

Example

```
(LET ((items (LIST "First Entry" 2 3.14 "Last entry"))) index)
  (SETQ index (ASKCHOICE "Choose one item" "Ok" items NIL))
  (IF index
```

```

        (PRINTF "User chose item num %i with contents <%s>\n"
          index (STR (NTH index items))
        )
      )
    )
  )

```

Consider the case where you would like to ask the user to select a certain record in a table. The table shall be called ‘Article’ with attributes ‘Name’, ‘Number’, and ‘Prize’. The following code fragment shows how to use ASKCHOICE for asking to select a record with Prize larger than 10 and ordered by Name:

```

(LET ((query (SELECT Article, Name, Number, Prize from Article
  WHERE (> Prize 10) ORDER BY Name))
  (recs (MAPFIRST FIRST (REST query))) ; record pointers
  (items (MAPFIRST REST (REST query))) ; choices
  (titles (REST (FIRST query))) ; titles
  (index (ASKCHOICE "Choose" "Ok" items NIL titles))
  (rec (NTH index recs)))
; now rec holds the selected record (or NIL on cancel)
)

```

See also ASKCHOICESTR, ASKOPTIONS.

16.16.6 ASKCHOICESTR

ASKCHOICESTR prompts the user for entering a string value offering several pre-defined ones.

```
(ASKCHOICESTR title oktext strings default [titles])
```

Pops up a dialog allowing the user to choose one string out of many strings or to enter any other string in a separate string field. You can set the window title and the text of the ‘Ok’ button in *title* and *oktext* (strings or NIL for default values). In *strings* you specify a list of choices. You can use a multi-column format by providing each choice item as a list of sub-items. The initial value of the string field can be set in *default* (string or NIL for an empty string field). If the optional argument *titles* is specified and is non-NIL then a list header containing *titles* is shown. For using a multi-column format, specify *titles* as a list of column titles.

Both, *strings* and *titles*, can also be given as a memo and a string (instead of lists). If so, they are converted to lists automatically by calling (MEMOTOLIST *strings* TRUE) (see Section 16.13.3 [MEMOTOLIST], page 110) and (STRTOLIST *titles*) (see Section 16.12.23 [STRTOLIST], page 104) respectively.

ASKCHOICESTR returns the chosen string or NIL if the user canceled the dialog.

Example

```

(LET ((strings (LIST "Claudia" "Mats" "Ralphie"))) likebest)
  (SETQ likebest
    (ASKCHOICESTR "Who do you like the best?" "Ok" strings
      "My collies!")
  )
)
(IF likebest (PRINTF "User chose <%s>\n" likebest))

```


ASKBUTTON returns the number of the pressed button (starting with 0 for the first (left-most) button) or NIL if the user pressed the ‘Cancel’ button.

Examples

```
(LET ((buttons (LIST "At home" "In bed" "In front of my computer"))) index)
  (SETQ index (ASKBUTTON "Please answer:"
    "Where do you want to be tomorrow?" buttons "Don't know"))
  )
(IF index
  (PRINTF "User chose: <%s>\n" (NTH index buttons))
  )
)
```

```
(ASKBUTTON "Info" "MUIbase is great!" NIL NIL)
```

See also ASKCHOICE.

16.16.9 ASKMULTI

ASKMULTI prompts the user to enter various kinds of information.

```
(ASKMULTI title oktext itemlist)
```

ASKMULTI is a multi-purpose dialog. It opens a window with the specified title, a set of GUI objects for editing data, and two buttons (‘Ok’ and ‘Cancel’) for terminating the dialog. The text of the ‘Ok’ button can be set in *oktext* (string or NIL for default text). The set of GUI objects are specified in *itemlist* which is a list of items where each item has one of the following forms:

```
(LIST title "String" initial [help [secret]]) for editing one line of text,
(LIST title "Memo" initial [help]) for editing multi-line text,
(LIST title "Integer" initial [help]) for editing an integer,
(LIST title "Real" initial [help]) for editing a real,
(LIST title "Date" initial [help]) for editing a date,
(LIST title "Time" initial [help]) for editing a time,
(LIST title "Bool" initial [help]) for a Boolean field,
(LIST title "Choice" initial
  (LIST choice ...) [help]
) for a choice field.
(LIST title "ChoiceList" initial
  (LIST choice ...) [help]
) for selecting one item of a list.
(LIST title "Options" initial
  (LIST option ...) [help]
) for selecting several items of a list.
non-list-expr for static text
```

The title (string or NIL for no title) will be displayed to the left of the GUI object. If the initial value is NIL then a default value is used (e.g. an empty text field). For choice

fields the initial value must be the index (starting with 0) for the initial active entry, for choice list fields the initial value may be NIL (no item is activated), and for options fields the initial value must be a list of integers representing the indices (starting with 0) of the items that are initially selected. The optional help field (string) can be used for giving more information to the user about the usage of the field. For string fields an additional parameter ‘`secret`’ can be specified. If non-NIL then the contents of the string field are made invisible by displaying a bullet sign for each string character.

ASKMULTI returns a list of result values which the user has edited and acknowledged by pressing the ‘Ok’ button. Each result value of a field has the same format as the one for the initial value, e.g. for a choice list field the result value is the index of the selected item (or NIL if no item has been selected), or for an options field the result value is a list of integers representing the indices of the selected items. For static text a value of NIL is returned.

E.g. if you have specified a date field, a static text field, a choice field, an options field, and a string field with initial value "world", and the user has entered 11.11.1999, selected the choice entry with index number 2, selected the 3rd and 4th item in the options field, and left the string field untouched then the function returns the list (11.11.1999 NIL 2 (3 4) "world").

If the user cancels the dialog, NIL is returned.

Example

```
(ASKMULTI "Please edit:" NIL (LIST
  (LIST "N_ame" "String" "")
  (LIST "_Birthday" "Date" NIL)
  (LIST "_Sex" "Choice" 0 (LIST "male" "female"))
  (LIST "_Has car?" "Bool" NIL)
  (LIST "_Likes" "Options" (LIST 0 2)
    (LIST "Beer" "Wine" "Whisky" "Wodka" "Schnaps"))
  ))
)
```

Please see also the project ‘AskDemo.mb’ for further examples.

16.17 I/O Functions

This sections lists functions and variables for input and output (e.g. printing) of data.

16.17.1 FOPEN

FOPEN opens a file for reading/writing.

```
(FOPEN filename mode [encoding])
```

Opens the file specified by *filename* (string). The *mode* parameter (string) controls the access mode. Use ‘`w`’ to open a file for writing, ‘`a`’ to append to a file, and ‘`r`’ for reading from a file. You may also use other flags (or combination of flags) like ‘`r+`’ for reading and writing. There is no check done that tests if you have specified a valid flag string. However if the file can’t be opened, NIL is returned.

The optional parameter *encoding* controls the encoding of the file and is one of the following strings:

‘`none`’: No interpretation of characters is performed. Use this for binary files.

"UTF-8": Text is encoded in UTF-8. Reading and writing converts from/to UTF-8.

"locale":

Text is encoded in your system locale. On Windows this is the system's code page. On Mac OS and Linux it is the setting of the LANG and LC_* environment variables, see `man locale`. On Amiga it is the default 8 bit encoding.

"8-bit": Text is encoded in the default 8-bit codeset. On Windows, Mac OS and Linux this is the ISO-8859-1 (latin 1) encoding. On Amiga it is the system's default 8 bit encoding (same as 'locale').

"auto": The encoding is auto-detected. If the file is readable then the encoding is determined as follows: If all contents conform to UTF-8 then "UTF-8" is assumed. Else if the system's locale is not UTF-8 then "locale" is assumed. Otherwise "8-bit" is assumed. When writing and the encoding has not been determined yet then first the system's locale encoding is tried. If there were no conversion errors then "locale", otherwise "UTF-8" is used.

If no *encoding* parameter is given then "auto" is used.

FOPEN returns a file handle on success. On failure NIL is returned. If *filename*, *mode* or *encoding* are NIL then NIL is returned.

Examples

'(FOPEN "index.html" "w" "utf-8")' opens and returns a file handle for writing to the file 'index.html' and encoding it in UTF-8.

'(FOPEN "output.txt" "a+")' opens file 'output.txt' for appending it using the same text encoding as is already present in the file. Note that if you only specify "a" as mode then MUIbase might not be able to read the file and decide the existing encoding. In this case the encoding is decided when writing to the file (and might be different from the existing one).

See also FCLOSE, stdout, FFLUSH.

16.17.2 FCLOSE

FCLOSE closes a file.

(FCLOSE *file*)

Closes the given file. Returns 0 on success, NIL if an error has occurred. If *file* is NIL then 0 is returned (no error). After closing a file accessing the file handle is an illegal operation and results in aborting program execution with an error message.

See also FOPEN, FFLUSH.

16.17.3 stdout

The global variable `stdout` holds the file handle to MUIbase's standard output file. The output filename can be set in menu item 'Program - Output file' (see Section 7.2.12 [Program output file], page 37).

The output file is opened on the first access of this variable (e.g. when calling '(FPRINTF stdout ...)', or when calling '(PRINTF ...)'). The file is not pre-opened on program

execution. This avoids opening the file when no output is generated, e.g. when you simply want to do some calculations and change some record contents.

When opening the output file the mode parameter is either `"w"` or `"a+"` depending on the `'Append'` setting in menu item `'Program - Output file'`. The encoding is set to `"auto"`.

If MUIbase can't open the program output file then execution is aborted and an error message is generated.

See also `FOPEN`, `PRINTF`.

16.17.4 PRINT

`PRINT` converts an expression to a string and prints it.

```
(PRINT elem)
```

Converts the value of *elem* to a readable string and prints it to `stdout`. This function mainly exists for debug purposes.

See also `PRINTF`, `stdout`.

16.17.5 PRINTF

`PRINTF` prints a formatted string.

```
(PRINTF format [expr ...])
```

Formats a string using the given format string and arguments and prints it to `stdout`. Formatting is done like in `SPRINTF` (see Section 16.12.34 [`SPRINTF`], page 107).

`PRINTF` returns the number of output characters or `NIL` on failure. If *format* is `NIL` then `NIL` is returned.

Example: `'(PRINTF "%i days and %i week" 7 1)'` prints the string `"7 days and 1 week"` to `stdout` and returns 17.

See also `PRINT`, `FPRINTF`, `stdout`.

16.17.6 FPRINTF

`FPRINTF` prints a formatted string to a file.

```
(FPRINTF file format [expr ...])
```

Formats a string using the given format string and arguments and prints it to the specified file. Formatting is done like in `SPRINTF` (see Section 16.12.34 [`SPRINTF`], page 107).

`FPRINTF` returns the number of output characters or `NIL` on failure. If *file* is `NIL` then `FPRINTF` still returns the number of potentially written characters but no output is actually written. If *format* is `NIL` then `NIL` is returned.

See also `PRINTF`, `FOPEN`.

16.17.7 FERROR

`FERROR` checks if an file I/O error has occurred.

```
(FERROR file)
```

returns `TRUE` if an error for the given file has occurred, `NIL` otherwise. If `'file'` is `NIL`, `NIL` is returned.

See also `FEOF`, `FOPEN`, `FCLOSE`.

16.17.8 FEOF

FEOF checks for an end of file status.

(FEOF *file*)

Tests the end-of-file indicator for the given file and returns TRUE if it is set. Otherwise NIL is returned. If 'file' is NIL, NIL is returned.

See also FERROR, FTELL, FOPEN, FCLOSE.

16.17.9 FSEEK

FSEEK sets the read/write position in a file.

(FSEEK *file offset whence*)

Sets the read/write position for the given file. The new position, measured in bytes, is obtained by adding *offset* bytes to the position specified by *whence*. If *whence* is set to SEEK_SET, SEEK_CUR, or SEEK_END, the *offset* is relative to the start of the file, the current position, or end-of-file, respectively.

On success, FSEEK returns 0. Otherwise NIL is returned and the file position stays unchanged. If *file*, *offset*, or *whence* is NIL, or if *whence* is not one of the constant values SEEK_SET, SEEK_CUR, or SEEK_END then NIL is returned.

Note that after a read operation calling FSEEK with *whence* as SEEK_CUR is only supported for encoding "none".

See also FTELL, FOPEN, Pre-defined constants.

16.17.10 FTELL

FTELL returns the read/write position of a file.

(FTELL *file*)

Determines the current read/write position of the given file relative to the beginning of the file and returns it as an integer. If an error occurs or if 'file' is NIL, then NIL is returned.

Note that after a read operation calling FTELL is only supported for encoding "none".

See also FSEEK, FOPEN, FEOF.

16.17.11 FGETCHAR

FGETCHAR reads a character from a file.

(FGETCHAR *file*)

Returns the next character from the given file as a string or NIL if *file* is NIL, end of file has been reached, or an error has happened. If the next character is a null character, an empty string is returned.

See also FGETCHARS, FGETSTR, FPUTCHAR.

16.17.12 FGETCHARS

FGETCHARS reads characters from a file.

(FGETCHARS *num file*)

returns a string containing the next *num* characters from the given file. If end of file has been reached before reading *num* characters or if a null character has been read then only

these characters are returned. If *num* or *file* are NIL, *num* is negative, end of file has been reached before reading the first character, or a read error has happened then NIL is returned.

See also FGETCHAR, FGETSTR.

16.17.13 FGETSTR

FGETSTR reads a string from a file.

(FGETSTR *file*)

returns the next line of the given file as a string or NIL if *file* is NIL, end of file has been reached, or an error happened. The end of a line is detected if either a newline character or a null character is read, or if end of file is detected. In either case the string does not contain any newline characters.

See also FGETCHAR, FGETCHARS, FGETMEMO, FPUTSTR.

16.17.14 FGETMEMO

FGETMEMO reads a memo from a file.

(FGETMEMO *file*)

returns a memo that contains the contents of the given file up to the next null character or up to the end of file. If *file* is NIL, end of file has been reached before reading any characters, or an error occurred then NIL is returned.

See also FGETSTR, FPUTMEMO.

16.17.15 FPUTCHAR

FPUTCHAR writes a character to a file.

(FPUTCHAR *str file*)

Writes the first character of *str* to the given file. If *str* is empty, a null character is written, if *str* or *file* are NIL, nothing happens. Returns *str* or NIL in case an output error occurred.

See also FPUTSTR, FGETCHAR.

16.17.16 FPUTSTR

FPUTSTR writes a string to a file.

(FPUTSTR *str file*)

Prints *str* together with a newline character to the given file. If *str* or *file* are NIL, nothing happens. Returns *str* or NIL in case an output error occurred.

See also FPUTCHAR, FPUTMEMO, FGETSTR.

16.17.17 FPUTMEMO

FPUTMEMO writes a memo to a file.

(FPUTMEMO *memo file*)

Prints *memo* to the given file. If *memo* or *file* are NIL, nothing happens. Returns *memo* or NIL in case an output error occurred.

See also FPUTSTR, FGETMEMO.

16.17.18 FFLUSH

FFLUSH flushes pending data to a file.

(FFLUSH *file*)

Flushes all pending output for the given file. Returns 0 on success, NIL if an error occurred. If *file* is NIL then 0 is returned (no error).

See also FOPEN, FCLOSE.

16.18 Record Functions

This section lists functions that deal with records.

16.18.1 NEW

NEW allocates a new record for a table.

(NEW *table init*)

Allocates a new record in the given table. The parameter *init* specifies the record which should be used for initializing the new record. A value of NIL stands for the initial record.

NEW returns a record pointer to the new record.

The NEW function has the side effect of setting the program record pointer of the given table (see Section 5.2 [Tables], page 18) to the new record.

Example: '(NEW table NIL)' allocates a new record in the given table and initializes it with the initial record.

See also NEW*, DELETE, Tables.

16.18.2 NEW*

NEW* is the star version of NEW (see Section 16.18.1 [NEW], page 126).

(NEW* *table init*)

NEW* checks if you have specified a 'New' trigger function for the given table (see Section 16.29.8 [New trigger], page 146). If so then this trigger function is called for allocating the record and its result is returned. The *init* parameter can be used to specify a record with which the new record should be initialized (use NIL for the initial record).

If no trigger function has been specified, the function behaves like the NEW function.

Warning: With this function it is possible to write endless loops, e.g. if you have defined a 'New' trigger function for a table and this function calls NEW* to allocate the record.

See also NEW, DELETE*.

16.18.3 DELETE

DELETE deletes a record in a table.

(DELETE *table confirm*)

Deletes the current program record of the given table after an optional delete confirmation. The first argument specifies the table for which the current program record should be deleted, the second argument is a Boolean expression. If it is NIL then the record is deleted silently, if it is not NIL then the state of preferences menu item 'Confirm delete record' is checked. If it is not set, the record is deleted silently, otherwise the standard delete dialog

appears asking for confirmation. If the users cancels the delete operation then the record will not be deleted.

The return code of the `DELETE` function reflects the selected action. If it returns `TRUE` then the record has been deleted, otherwise (the user has canceled the operation) `NIL` is returned.

On deletion, `DELETE` sets the program record pointer (see Section 5.2 [Tables], page 18) of the specified table to `NIL`.

Example: `'(DELETE table NIL)'` deletes the current record in the given table silently.

See also `DELETE*`, `DELETEALL`, `NEW`, Tables.

16.18.4 DELETE*

`DELETE*` is the star version of `DELETE` (see Section 16.18.3 [`DELETE`], page 126).

`(DELETE* table confirm)`

`DELETE*` checks if you have specified a `'Delete'` trigger function for the given table (see Section 16.29.9 [Delete trigger], page 147). If so then this trigger function is called for deleting the record and its result is returned. The *confirm* parameter can be used to specify if the trigger function should pop up a confirmation dialog before deleting the record.

If no trigger function has been specified, the function behaves like the `DELETE` function.

Warning: With this function it is possible to write endless loops, e.g. if you have defined a `'Delete'` trigger function for a table and this function calls `DELETE*` to delete the record.

See also `DELETE`, `DELETEALL`, `NEW*`.

16.18.5 DELETEALL

`DELETEALL` deletes all records of a table.

`(DELETEALL table[*])`

Deletes all records of the specified table. If you add a star behind the table name then only those records that match the current filter of the table are deleted. There is no confirmation dialog before deleting the records.

`DELETEALL` returns `TRUE` on successful deletion of all records, otherwise `NIL` is returned. If *table* is `NIL` then `NIL` is returned.

Example: `'(DELETEALL table*)'` deletes all records in the given table that match the filter of the table.

See also `DELETE`, Tables.

16.18.6 GETMATCHFILTER

`GETMATCHFILTER` returns the match-filter state of a record.

`(GETMATCHFILTER rec)`

Returns `TRUE` if the specified record matches the filter of its table, `NIL` otherwise. If the filter of the table is currently not active then `TRUE` is returned. If *rec* is `NIL` (the initial record) then `NIL` is returned.

See also `SETMATCHFILTER`, `GETISSORTED`, `GETFILTERSTR`, `SETFILTERSTR`.

16.18.7 SETMATCHFILTER

SETMATCHFILTER sets the match-filter state of a record.

(SETMATCHFILTER *rec on*)

Changes the match-filter state of the specified record to the value of *on*. SETMATCHFILTER returns the new match-filter state of the given record. The new state may be different from the expected one because setting the match-filter state to NIL does only work when the filter of the corresponding table is currently active, otherwise TRUE is returned. Calling SETMATCHFILTER with a value of NIL for *rec* (the initial record) will always return NIL.

See also GETMATCHFILTER, SETISSORTED, GETFILTERSTR, SETFILTERSTR.

16.18.8 GETISSORTED

GETISSORTED returns the sorted state of a record.

(GETISSORTED *rec*)

Returns TRUE if the specified record is sorted in the order that has been defined for its table, NIL otherwise. If *rec* is NIL then NIL is returned.

See also SETISSORTED, SETMATCHFILTER, REORDER, GETORDERSTR, SETORDERSTR, Comparison function.

16.18.9 SETISSORTED

SETISSORTED sets the sorted state of a record.

(SETISSORTED *rec on*)

Changes the sorted state of the specified record to the value of *on*. Use this function if you think that a certain record is in the right order (*on* = TRUE), or it it should be reordered (*on* = NIL). Reordering all unsorted records can be done by calling the REORDER function (see Section 16.20.4 [REORDER], page 131).

SETISSORTED returns the new sorted state of the given record. Calling SETISSORTED with a value of NIL for *rec* (the initial record) will return NIL.

For an example on how to use this function, see Section 16.29.10 [Comparison function], page 147.

See also GETISSORTED, SETMATCHFILTER, REORDER, GETORDERSTR, SETORDERSTR, Comparison function.

16.18.10 RECNUM

RECNUM returns the record number of a record.

(RECNUM *record*)

Returns the record number of the given record. Please note that the numbering for records is different than e.g. for lists. For lists, strings and others the counting begins with zero, however for records it begins with 1 for the first record. The number 0 is reserved for the initial record. This seems to be inconsistent with the rest of the MUIbase programming functions, but it does really makes sense here as the record numbers are also used in the window display.

See also RECORDS, INT.

16.18.11 COPYREC

COPYREC copies records.

(COPYREC *rec source*)

Copies the contents of record *source* to record *rec*. If *source* is NIL then *rec* is set to the values of the initial record. If *rec* is NIL then an error message is generated.

COPYREC returns *rec*.

See also NEW.

16.19 Attribute Functions

This section lists functions that work on attributes of a table.

16.19.1 ATTRNAME

ATTRNAME returns the name of an attribute.

(ATTRNAME *attr*)

Returns a string containing the name of the specified attribute.

See also TABLENAME

16.19.2 MAXLEN

MAXLEN returns the maximum size of a string attribute.

(MAXLEN *string-attr*)

Returns the maximum number of characters that the given string attribute can hold.

See also LEN.

16.19.3 GETLABELS

GETLABELS returns all labels of a choice or string attribute.

(GETLABELS *attr*)

Returns the labels of the given choice or string attribute. In case of a choice attribute, the labels you entered in the attribute dialog (see Section 15.2.2 [Type specific settings], page 61) are returned, in case of a string attribute, the static labels you entered for the list-view pop-up (see Section 15.3.3 [Attribute object editor], page 66) are returned (note that this function is only useful for static labels).

The labels are returned in one single string and are separated by newline characters.

For example, consider you have a choice attribute with the labels 'Car', 'House', and 'Oil'. Then calling GETLABELS on that attribute will result to the string "Car\nHouse\nOil".

Note: you can easily convert the result string to a list by calling MEMOTOLIST (see Section 16.13.3 [MEMOTOLIST], page 110) on the result string.

See also SETLABELS.

16.19.4 SETLABELS

SETLABELS is used to set the labels of a string attribute.

```
(SETLABELS attr str)
```

Sets the static labels of the string attribute *attr* to the labels listed in the *str* argument. The *str* argument consists of lines each of which holds one label. The labels replace the ones you have entered for the pop-up list-view in the attribute object editor (see Section 15.3.3 [Attribute object editor], page 66). Note that this function is only useful for static labels.

SETLABELS returns the value of its *str* argument.

Example: '(SETLABELS Table.String "My house\nis\nyour house")' sets the static list-view labels of the specifies string attribute to 'My house', 'is', and 'your house'.

Note: you can easily convert a list of labels to the required string format by calling LISTTOMEMO on the list.

See also GETLABELS.

16.20 Table Functions

16.20.1 TABLENAME

TABLENAME returns the name of a table.

```
(TABLENAME table)
```

Returns a string containing the name of the specified table.

See also ATTRNAME

16.20.2 GETORDERSTR

GETORDERSTR returns the record order of a table.

```
(GETORDERSTR table)
```

Returns the current order expression of the given table. If the table uses an attribute list for ordering then the returned string contains the attribute names separated by spaces. Each attribute name is prepended by a '+' or a '-' sign indicating ascending or descending order.

If the table is ordered by a comparison function then the name of this function is returned.

An empty string means no ordering.

Example

Consider a table 'Person' which is ordered by the Attributes 'Name' (ascending), 'Town' (ascending), and 'Birthday' (descending). Then '(ORDERSTR Person)' will result to the string "+Name +Town -Birthday".

See also SETORDERSTR, REORDER, REORDERALL, GETISSORTED, SETISSORTED, Order, Comparison function.

16.20.3 SETORDERSTR

SETORDERSTR sets the record order of a table.

```
(SETORDERSTR table order)
```


Sets the order of the given table according to the *order* string. The *order* string can either hold a list of attribute names or the name of a comparison function.

For sorting using an attribute list, the *order* string must contain the attribute names separated by any number of spaces, tabs or newlines. Each attribute name may be prepended by a '+' or a '-' sign indicating ascending or descending order. If you omit this sign then ascending ordering is assumed.

For sorting using a comparison function, the *order* string must hold the name of the function.

SETORDERSTR returns TRUE if it has been able to set the new order, NIL otherwise, e.g. if an unknown attribute has been specified or the type of the attribute is not allowed for ordering. If you specify NIL for the *order* argument then nothing happens and NIL is returned.

Note: For building the order string you should not directly write the attribute names into the string because when you change an attribute name then the order string will not be updated. Better use the ATTRNAME function (see Section 16.19.1 [ATTRNAME], page 129) to copy the attribute's name into the order string.

Example

Consider a table 'Person' with the attributes 'Name', 'Town', and 'Birthday'. Then '(SETORDERSTR Person (SPRINTF "+%s" (ATTRNAME Person.Name)))' will set the order of table 'Person' using 'Name' as (ascending) order attribute.

See also GETORDERSTR, REORDER, REORDERALL, GETISSORTED, SETISSORTED, Order, Comparison function.

16.20.4 REORDER

REORDER brings all unsorted records back into the right order.

(REORDER *table*)

Examines all records of the given table for unsorted ones and reinserts them to their right positions. After reinserting an unsorted record, the sorted state of the record is set to TRUE, thus on the return of REORDER the sorted state of all records is TRUE.

REORDER returns NIL.

Usually you only need to call this function, when you are using a comparison function for defining the order of a table. Orders defined by an attribute list are automatic, that is, a record is reordered automatically when needed.

For an example on how to use this function, see Section 16.29.10 [Comparison function], page 147.

See also REORDERALL, GETORDERSTR, SETORDERSTR, GETISSORTED, SETISSORTED, Order, Comparison function.

16.20.5 REORDERALL

REORDERALL reorders all records of a table.

(REORDERALL *table*)

Reorders all records of the given table by setting the sorted state of all records to NIL and then calling REORDER for reordering everything.

REORDERALL returns NIL.

See also REORDER, GETORDERSTR, SETORDERSTR, GETISSORTED, SETISSORTED, Order, Comparison function.

16.20.6 GETFILTERACTIVE

GETFILTERACTIVE returns the filter state of a table.

```
(GETFILTERACTIVE table)
```

Returns TRUE if the filter of the specified table is currently activated and NIL otherwise.

See also SETFILTERACTIVE, GETFILTERSTR, GETMATCHFILTER.

16.20.7 SETFILTERACTIVE

SETFILTERACTIVE sets the filter state of a table.

```
(SETFILTERACTIVE table bool)
```

Sets the filter state of the specified table. If *bool* is non-NIL then the filter is activated, otherwise it is deactivated.

SETFILTERACTIVE returns the new state of the filter. The new state may not be the expected one in case you activate the filter but an error condition occurs and the filter can't be activated. However deactivating the filter always succeeds.

See also GETFILTERACTIVE, SETFILTERSTR, SETMATCHFILTER.

16.20.8 GETFILTERSTR

GETFILTERSTR returns the record filter expression of a table.

```
(GETFILTERSTR table)
```

Returns the record filter expression of the specified table as a string. An empty string means that no filter expression has been set for this table.

See also SETFILTERSTR, GETFILTERACTIVE, GETMATCHFILTER.

16.20.9 SETFILTERSTR

SETFILTERSTR sets the record filter expression of a table.

```
(SETFILTERSTR table filter-str)
```

Sets the record filter expression of the specified table to the expression in the *filter-str* argument (which must be a string and not the actual expression itself!). If the filter of the given table is currently active then the new filter expression is directly applied to all records and the match-filter state of all records are recomputed.

SETFILTERSTR returns TRUE if it has been able to compile the given filter string expression, otherwise NIL is returned. Note that you only get the result of the compilation. If the filter of the given table is currently active and recomputing all match-filter states of the corresponding records fails then you will not notice that from the result of this function. The recommended way to set a new filter expression is like follows:

```
(SETFILTERACTIVE Table NIL) ; always succeeds.
(IF (NOT (SETFILTERSTR Table filter-string))
  (ERROR "Can't set filter string for %s!" (TABLENAME Table))
)
```

```
(IF (NOT (SETFILTERACTIVE Table TRUE))
  (ERROR "Can't activate filter for %s!" (TABLENAME Table))
)
```

If SETFILTERSTR is called with a value of NIL for the *filter-str* argument then nothing happens and NIL is returned.

Example: '(SETFILTERSTR Table "> Value 0.0)")'.

See also GETFILTERSTR, SETFILTERACTIVE, SETMATCHFILTER.

16.20.10 RECORDS

RECORDS returns the number of records in a table.

```
(RECORDS table)
```

Returns the number of records in the given table. You may append a star to the table name for counting the number of records that match the filter of the table.

See also RECORD, RECNUM.

16.20.11 RECORD

RECORD returns a record pointer for a given record number.

```
(RECORD table num)
```

Returns the record pointer to the *num*-th record in the given table or NIL if a record with this number doesn't exist. You may add a star to the table name to get the *num*-th record that matches the record filter of the table.

Please note that record numbers start with 1 and record number 0 is used for the initial record.

See also RECORDS, RECNUM.

16.20.12 SELECT

SELECT extracts and returns various data from records.

```
(SELECT [DISTINCT] exprlist FROM tablelist
  [WHERE where-expr] [ORDER BY orderlist])
```

where *exprlist* is either a simple star '*' or a list of expressions with optional titles separated by commas:

```
exprlist:      * | expr "title", ...
```

and *tablelist* is a list of table names:

```
tablelist:     table[*] [ident], ...
```

For each table in the table list you can specify an identifier. This can be very useful if a table occurs more than once in the table list (see example of comparing ages below). If you add a star to a table then only the records matching the currently defined filter of that table will be examined.

The orderlist has the following syntax:

```
orderlist:     expr [ASC | DESC], ...
```

where *expr*, ... can be arbitrary expressions or field numbers. For example '(SELECT Name FROM ... ORDER BY 1)' will sort the result by the 'Name' attribute. You may specify ASC or DESC for an ascending or descending order. If none of them are present then an ascending order is assumed.

How it works

The select-from-where query builds the (mathematical) cross product of all tables in the table list (it examines all sets of records in *table*, . . .) and checks the where-expression (if any). If the where-expression results to TRUE (or there is no where-expression) then a list is build whose elements are calculated by the expression list in the select-part. If you have specified a single star for the expression list then the list contains the values of all attributes belonging to tables in the table list (except virtual attributes and buttons).

The result of the query is a list of lists. The first list entry contains the title strings, the remaining ones contain the values of the from-list in the matching records.

Examples

See Section 14.6 [Query examples], page 56, for some examples using the `SELECT` function.

See also `FOR ALL`.

16.21 GUI Functions

This section describes functions for manipulating GUI elements.

16.21.1 SETCURSOR

`SETCURSOR` sets the cursor on a GUI element.

`(SETCURSOR attr-or-table)`

Sets the cursor on the GUI object of the given attribute or table. The function also opens the window where the attribute/table resides in if the window was not open.

`SETCURSOR` returns TRUE if everything went ok (window could be opened) or NIL on failure.

See also `SETVIRTUALLISTACTIVE`.

16.21.2 SETBGPEN

`SETBGPEN` sets the background pen of a GUI element.

`(SETBGPEN attr pen)`

Sets the pen for drawing the background of the GUI object given by *attr*. For *pen* a hexadecimal integer value holding a color in RGB (red, green, blue) format, or one of the `PEN_*` constants can be used. If *pen* is NIL then a default background is set.

`SETBGPEN` returns the value of the new background pen.

Example: `'(SETBGPEN Control.Status 0xFF0000)'` sets a red background for the GUI element of attribute `'Status'` in table `'Table'`. The same effect can be achieved by `'(SETBGPEN Control.Status PEN_RED)'`.

See also Pre-defined constants.

16.21.3 GETWINDOWOPEN

`GETWINDOWOPEN` returns the open state of a window.

`(GETWINDOWOPEN attr-or-table)`

Returns the open state of the window where the given attribute/table resides.

See also `SETWINDOWOPEN`.

16.21.4 SETWINDOWOPEN

SETWINDOWOPEN opens and closes a window.

```
(SETWINDOWOPEN attr-or-table open)
```

Opens or closes the window in which the given attribute/table resides. If *open* is non-NIL then the window is opened, otherwise it is closed. You cannot close the main window of a project.

SETWINDOWOPEN returns the new open state of the window.

See also GETWINDOWOPEN.

16.21.5 GETVIRTUALLISTACTIVE

GETVIRTUALLISTACTIVE returns the index of the active line of a virtual attribute that uses the ‘List’ kind for display.

```
(GETVIRTUALLISTACTIVE virtual-attr)
```

Returns the logical index (starting with 1) of the currently active line in the specified virtual attribute. The logical index is the line number in the original list used when setting the virtual attribute. It can differ from the display order in case the user changed the sorting, e.g. by clicking on a column title. If the GUI element of *virtual-attr* is not visible, or if it does not use the ‘List’ kind for display, or if no line is active, then NIL is returned.

See also SETVIRTUALLISTACTIVE.

16.21.6 SETVIRTUALLISTACTIVE

SETVIRTUALLISTACTIVE sets the active line of a virtual attribute that uses the ‘List’ kind for display.

```
(SETVIRTUALLISTACTIVE virtual-attr num)
```

Sets the active line of the given virtual attribute to the *num*-th logical line (starting with 1). The logical line is the line number in the original list used when setting the virtual attribute and can differ from the display order in case the user changed the sorting, e.g. by clicking on a column title.

Returns *num*, or NIL if the GUI element of *virtual-attr* is not visible, does not use the ‘List’ kind for display, or if *num* is out of range (less than 1 or greater than the number of lines).

SETVIRTUALLISTACTIVE does not set the cursor to the attribute’s GUI element, use SETCURSOR (see Section 16.21.1 [SETCURSOR], page 134) for doing so.

See also GETVIRTUALLISTACTIVE, SETCURSOR.

16.22 Project Functions

This section lists functions dealing with projects.

16.22.1 PROJECTNAME

PROJECTNAME returns the project name.

```
(PROJECTNAME)
```

`PROJECTNAME` returns the name of the current project as a string or `NIL` if no name has been defined yet. The project name is the pathname of the project directory in the file system.

See also `CHANGES`.

16.22.2 PREPARECHANGE

`PREPARECHANGE` prepares the project for a change.

(`PREPARECHANGE`)

This command obtains a change lock on the project. This is useful when accessing a project with several MUIbase instances possibly running on different computers. Once a change lock has been obtained, no other MUIbase instance can obtain one until the lock is released. The change lock is released if the project program returns without actually performing a change, or after the project has been saved. For more information on sharing of a project, see Section 6.1 [File format], page 28.

`PREPARECHANGE` returns `NIL` on success. If obtaining the change lock fails, the program quits with an appropriate error message.

See also `CHANGES`.

16.22.3 CHANGES

`CHANGES` returns the number of changes in the current project.

(`CHANGES`)

Returns an integer containing the number of changes since the last save operation of the current project.

See also `PREPARECHANGE`, `PROJECTNAME`.

16.22.4 GETADMINMODE

`GETADMINMODE` tells whether the current project is in admin mode or user mode.

(`GETADMINMODE`)

Returns `TRUE` if the current project is in admin mode, `NIL` otherwise.

See also `SETADMINMODE`, `ADMINPASSWORD`, `onAdminMode`.

16.22.5 SETADMINMODE

`SETADMINMODE` changes the current project to admin mode or user mode.

(`SETADMINMODE` *admin*)

If *admin* is `NIL` then the current project is set into user mode, otherwise into admin mode. Note that there is no authentication dialog when changing from user to admin mode using this function.

Returns `TRUE` if the project has been set to admin mode, or `NIL` if set to user mode.

See also `GETADMINMODE`, `ADMINPASSWORD`, `onAdminMode`, `demo Users.mb`.

16.22.6 ADMINPASSWORD

ADMINPASSWORD obtains the admin password as SHA1 hash string.

(ADMINPASSWORD)

Returns a string containing the SHA1 hash of the admin password of the current project. If no admin password has been set, NIL is returned.

See also GETADMINMODE, SETADMINMODE, SHA1SUM, demo `Users.mb`.

16.23 System Functions

This section lists functions accessing the operating system.

16.23.1 EDIT

EDIT launches the external editor.

(EDIT *filename*)

Starts the external editor for editing the specified file. The external editor can be set in menu item ‘Preferences - External editor’ (see Section 7.1.2 [External editor], page 32). EDIT starts the external editor synchronously, that is, it waits until the user exits the editor.

EDIT returns the return code of the external editor as an integer.

See also EDIT*, VIEW, SYSTEM.

16.23.2 EDIT*

EDIT* is the star version of EDIT and has the same effect as EDIT (see Section 16.23.1 [EDIT], page 137). The only difference is that EDIT* starts the external editor asynchronously, thus the function returns immediately.

EDIT* returns 0 if it was successful in starting the editor, otherwise it returns a non-zero integer value representing a system specific error code.

See also EDIT, VIEW*, SYSTEM*.

16.23.3 VIEW

VIEW launches the external viewer.

(VIEW *filename*)

Starts the external viewer for displaying the specified file. The external viewer can be set in menu item ‘Preferences - External viewer’ (see Section 7.1.3 [External viewer], page 33). VIEW starts the external viewer synchronously, that is, it waits until the user exits the viewer. Note that on some systems, the call might return immediately if an instance of the viewer is already running.

VIEW returns the return code of the external viewer as an integer.

See also VIEW*, EDIT, SYSTEM.

16.23.4 VIEW*

VIEW* is the star version of VIEW and has the same effect as VIEW (see Section 16.23.3 [VIEW], page 137). The only difference is that VIEW* starts the external viewer asynchronously, thus the function returns immediately.

VIEW* returns 0 if it was successful in starting the viewer, otherwise it returns a non-zero integer value representing a system specific error code.

See also **VIEW**, **EDIT***, **SYSTEM***.

16.23.5 SYSTEM

SYSTEM calls an external program.

(**SYSTEM** *fmt* [*arg* ...])

Calls an external program. The command line to call the program is generated from *fmt* and the optional arguments like in the **SPRINTF** function (see Section 16.12.34 [**SPRINTF**], page 107). For interpreting the command line, a system specific shell is used (ShellExecute on Windows, /bin/sh on Mac OS and Linux, the user shell on Amiga). **SYSTEM** waits until the called program exits.

SYSTEM returns the return code of the executed command as an integer.

See also **SYSTEM***, **EDIT**, **VIEW**.

16.23.6 SYSTEM*

SYSTEM* is the star version of **SYSTEM** and has the same effect as **SYSTEM** (see Section 16.23.5 [**SYSTEM**], page 138). The only difference is that **SYSTEM*** executes the command line asynchronously, thus the function returns immediately.

SYSTEM* returns 0 if it was successful in starting execution of the command line, otherwise it returns a non-zero integer value representing a system specific error code.

See also **SYSTEM**, **EDIT***, **VIEW***.

16.23.7 STAT

STAT examines a filename.

(**STAT** *filename*)

Examines if the specified filename exists in the file system. **STAT** returns NIL if the filename could not be found, 0 if the filename exists and is a directory, and an integer value greater than 0 if the filename exists and is a regular file.

16.23.8 TACKON

TACKON creates a pathname.

(**TACKON** *dirname* [*component* ...])

Joins *dirname* and all components in [*component* ...] to a pathname. **TACKON** knows how to deal with special characters used as path separators at the end of each argument. It returns the pathname as a string or NIL if any of the arguments is NIL. Note that **TACKON** does not perform any check whether the resulting path actually refers to an existing file or directory in the filesystem.

Example: '(**TACKON** "Sys:System" "CLI")' results to "Sys:System/CLI".

See also **FILENAME**, **DIRNAME**.

16.23.9 FILENAME

FILENAME extracts the filename part of a path name.

```
(FILENAME path)
```

Extracts the last component of the given path name. There is no check whether *path* actually refers to a file, thus it is also possible to use FILENAME to get the name of a sub-directory. FILENAME returns its result as a string or NIL if *path* is NIL.

Example: ‘(FILENAME "Sys:System/CLI")’ results to "CLI".

See also DIRNAME, TACKON.

16.23.10 DIRNAME

DIRNAME extracts the directory part of a path name.

```
(DIRNAME path)
```

Extracts the directory part of the given path name. There is no check whether *path* actually refers to a file, thus it is also possible to use DIRNAME to get the name of a parent directory. DIRNAME returns its result as a string or NIL if *path* is NIL.

Example: ‘(DIRNAME "Sys:System/CLI")’ results to "Sys:System".

See also FILENAME, TACKON.

16.23.11 MESSAGE

MESSAGE displays a message to the user.

```
(MESSAGE fmt [arg ...])
```

Sets the window title of the pause/abort window (if it is open). The title string is generated from *fmt* and the optional arguments like in the SPRINTF function (see Section 16.12.34 [SPRINTF], page 107).

MESSAGE returns the formatted title string.

Example: ‘(MESSAGE "6 * 7 = %i" (* 6 7))’.

See also PRINT, PRINTF.

16.23.12 COMPLETEMAX

COMPLETEMAX sets the maximum number of progress steps.

```
(COMPLETEMAX steps)
```

Sets the maximum number of steps for showing the progress of your MUIbase program to the user. The default (if you do not call this function) is 100 steps. The argument *steps* must be an integer value. If *steps* is NIL or 0 then no progress bar is displayed. The progress bar is part of the pause/abort window that pops up after a short delay when executing a MUIbase program.

COMPLETEMAX returns its argument *steps*.

See also COMPLETEADD, COMPLETE.

16.23.13 COMPLETEADD

COMPLETEADD increases the progress state.

```
(COMPLETEADD add)
```

Adds the integer expression *add* to the current progress value. Initially, the progress value is set to 0. If *add* is NIL then the progress value is reset to 0 and no progress bar is shown.

COMPLETEADD returns its argument *add*.

Example:

```
(SETQ num ...)
(COMPLETEMAX num)
(DOTIMES (i num)
  (COMPLETEADD 1)
)
```

See also COMPLETEMAX, COMPLETE.

16.23.14 COMPLETE

COMPLETE sets the progress state.

```
(COMPLETE cur)
```

Sets the current progress value to the integer expression *cur*. If *cur* is NIL or 0 then no progress bar is shown.

COMPLETE returns its argument *cur*.

Example:

```
(COMPLETE 10)
...
(COMPLETE 50)
...
(COMPLETE 100)
```

See also COMPLETEMAX, COMPLETEADD.

16.23.15 GC

GC forces garbage collection.

```
(GC)
```

Forces garbage collection and returns NIL. Normally garbage collection is done automatically from time to time.

16.23.16 PUBSCREEN

PUBSCREEN returns name of public screen.

```
(PUBSCREEN)
```

On Amiga, PUBSCREEN returns the name of the public screen MUIbase is running on, or NIL in case the screen is not public.

On other systems PUBSCREEN returns NIL.

16.24 Pre-Defined Variables

MUIbase knows some pre-defined global variables.

In the current version there exists only one global variable: `stdout` (see Section 16.17.3 [stdout], page 122).

16.25 Pre-Defined Constants

The following pre-defined constants can be used in any expression for programming.

Name	Type	Value	Comment
NIL	any	NIL	
TRUE	Boolean	TRUE	
RESET	string	"\33c"	
NORMAL	string	"\33[0m"	
ITON	string	"\33[3m"	
ITOFF	string	"\33[23m"	
ULON	string	"\33[4m"	
ULOFF	string	"\33[24m"	
BFON	string	"\33[1m"	
BFOFF	string	"\33[22m"	
ELITEON	string	"\33[2w"	
ELITEOFF	string	"\33[1w"	
CONDON	string	"\33[4w"	
CONDOFF	string	"\33[3w"	
WIDEON	string	"\33[6w"	
WIDEOFF	string	"\33[5w"	
NLQON	string	"\33[2\"z"	
NLQOFF	string	"\33[1\"z"	
INT_MAX	integer	2147483647	Maximum integer value
INT_MIN	integer	-2147483648	Minimum integer value
HUGE_VAL	real	1.797693e+308	Largest absolute real value
PI	real	3.14159265359	
OSTYPE	string	<OS type>	"Windows", "MacOSX", "Unix" or "Amiga"
OSVER	integer	<OS version>	
OSREV	integer	<OS revision>	
MBVER	integer	<MUIbase version>	
MBREV	integer	<MUIbase revision>	
LANGUAGE	string	depends	Default language
SEEK_SET	integer	see stdio.h	Seek from beg. of file
SEEK_CUR	integer	see stdio.h	Seek from current pos
SEEK_END	integer	see stdio.h	Seek from end of file
TMPDIR	string	Temporary directory depending on system	
PEN_WHITE	integer	0xFFFFFFFF	
PEN_BLACK	integer	0x000000	
PEN_RED	integer	0xFF0000	
PEN_GREEN	integer	0x00FF00	

PEN_BLUE	integer	0x0000FF
PEN_CYAN	integer	0x00FFFF
PEN_MAGENTA	integer	0xFF00FF
PEN_YELLOW	integer	0xFFFF00

See Section 16.4.7 [Constants], page 80, for more information about constants. For defining your own constants, use the `#define` preprocessing directive (see Section 16.3.1 [#define], page 75).

16.26 Functional Parameters

You can pass a function as an argument to another function. This is useful for defining functions of higher order, e.g. for sorting or mapping a list.

To call a function that has been passed in an argument you have to use the `FUNCALL` function (see Section 16.6.6 [FUNCALL], page 85).

Example:

```
(DEFUN map (l fun)                # arguments: list and function
  (LET (res)                      # local variable res, initialized with NIL
    (DOLIST (i l)                 # for all items one by one
      (SETQ res
        (CONS (FUNCALL fun i) res) # calls function and
      )                               # build new list
    )
  (REVERSE res)                  # we need to reverse the new list
)
```

You can now use the `map` function for example to increment all items of a list of integers:

`'(map (LIST 1 2 3 4) 1+)'` results to `(2 3 4 5)`.

See also `FUNCALL`, `APPLY`, `MAPFIRST`.

16.27 Type Specifiers

It is possible to specify the type of a variable by adding a type specifier behind the name. The following type specifiers exist:

Specifier	Description
:INT	for integers
:REAL	for reals
:STR	for strings
:MEMO	for memos
:DATE	for dates
:TIME	for times
:LIST	for lists
:FILE	for file handles

```
:FUNC      for functions of any type
:table     for record pointers to table
```

The type specifier appends the variable name as in the following example:

```
(LET (x:INT (y:REAL 0.0) z) ...)
```

The example defines three new variables ‘x’, ‘y’ and ‘z’, where ‘x’ is of type integer and initialized with NIL, ‘y’ is of type real and initialized with 0.0, and ‘z’ is an untyped variable initialized with NIL.

The advantage of the type specifiers is that the compiler can detect more type errors, e.g. if you have a function:

```
(DEFUN foo (x:INT) ...)
```

and call it with ‘(foo "bar")’ then the compiler generates an error message. However, if you call ‘foo’ with an untyped value, e.g. ‘(foo (FIRST list))’ then no error checking can be done at compile time because the type of ‘(FIRST list)’ is unknown.

For reasons of speed no type checking is currently done at run time. It could be implemented but then would add a little overhead which is not really necessary as the wrong type will result in a type error sooner or later anyway.

Type specifiers for record pointers have another useful feature. If you tag a variable as a record pointer to a table then you can access all attributes of this table by using the variable name instead of the table name in the attribute path. E.g. if you have a table ‘Foo’ with an attribute ‘Bar’, and you define a variable ‘foo’ as:

```
(LET (foo:Foo))
```

then you can print the ‘Bar’ attribute of the third record by using:

```
(SETQ foo (RECORD Foo 3)) (PRINT foo.Bar)
```

Note that in a select-from-where expression, variables defined in the from list automatically have a type of record pointer to the corresponding table.

16.28 Semantics of Expressions

The semantics of expressions are very important for understanding what a program does. This section lists the semantics depending on syntactical expressions.

(*func* [*expr* ...])

Evaluates *expr* ... and then calls the function *func* (call by value). Returns the return value of the called function. In MUIbase there exists some non-strict functions, e.g. AND, OR and IF. These functions may not evaluate all expressions. For more information about non-strict functions, see Section 16.4.2 [Lisp syntax], page 77, Section 16.9.1 [AND], page 93, Section 16.9.2 [OR], page 94, and Section 16.6.8 [IF], page 85.

(*expr* ...)

Evaluates *expr* ... and returns the value of the last expression (see Section 16.6.1 [PROGN], page 83). An empty expression () evaluates to NIL.

Table

Returns the program record pointer of the given table.

*Table**

Returns the GUI record pointer of the given table.

AttrPath

Returns the contents of the specified attribute. The attribute path specifies which record is used to extract the attribute value. For example ‘*Table.Attribute*’ uses the program record of ‘*Table*’ to extract the value of the attribute, ‘*Table.ReferenceAttribute.Attribute*’ uses the program record of ‘*Table*’ to extract the value of the reference attribute (which is a record pointer) and then uses this record to extract the value of ‘*Attribute*’.

var

Returns the contents of the global or local variable *var*. Global variables can be defined with **DEFVAR** (see Section 16.5.3 [DEFVAR], page 82), local variables e.g. with **LET** (see Section 16.6.3 [LET], page 83).

var.AttrPath

Uses the record pointer of *var* to determine the value of the specified attribute.

16.29 Function Triggering

For automatic execution of MUIbase programs you can specify trigger functions for projects, tables and attributes which are called in specific cases. This section lists all available trigger possibilities.

16.29.1 onOpen

After opening a project, MUIbase searches the project’s program for a function called **onOpen**. If such a function exists then this function is called without any arguments.

Example

```
(DEFUN onOpen ()
  (ASKBUTTON NIL "Thank you for opening me!" NIL NIL)
)
```

See also **onReload**, **onClose**, **onAdminMode**, **onChange**, **demo Trigger.mb**.

16.29.2 onReload

Similar to **onOpen** (see Section 16.29.1 [onOpen], page 144) MUIbase calls the function **onReload** when reloading a project, e.g. by selecting menu item ‘**Project - Reload**’. The function is called without any arguments.

However, **onReload** is only called in case there are no structural changes to the project, i.e. no tables or attributes were changed, added or deleted, no changes to the project program were made, and no other changes are present that qualify as a structural change. In such a case, a reload is considered a re-opening of the project, and the function **onOpen** is called instead.

See also **onOpen**, **onClose**, **onAdminMode**, **onChange**.

16.29.3 onClose

Before closing a project, MUIbase searches the project's program for a function called `onClose`. If such a function exists then this function is called without any arguments. In the current version the result of the trigger function is ignored and the project is closed regardless of its return value.

If you do changes to the project in the `onClose` function then MUIbase will ask you for saving the project first before it is actually closed. If you use menu item 'Project - Save & Close' for closing the project, the trigger function is called before saving the project, thus the changes are saved automatically.

Example

```
(DEFUN onClose ()
  (ASKBUTTON NIL "Good bye!" NIL NIL)
)
```

See also `onOpen`, `onChange`, `demo Trigger.mb`.

16.29.4 onAdminMode

Whenever a project is set into admin mode or user mode and a function called `onAdminMode` exists in the project's program then this function is called. The function receives one argument *admin* telling whether the project is in admin mode (*admin* is non-NIL) or in user mode (*admin* is NIL).

Example

```
(DEFUN onAdminMode (admin)
  (IF admin
    (ASKBUTTON NIL "Now in admin mode" NIL NIL)
    (ASKBUTTON NIL "Back to user mode" NIL NIL)
  )
)
```

See also `onOpen`, `onChange`, `SETADMINMODE`, `demo Users.mb`.

16.29.5 onChange

Whenever the user makes changes to a project or after saving a project, MUIbase searches the project's program for a function called `onChange`. If such a function exists then this function is called without any arguments. This can be used to count the changes a user does to a project.

Example

```
(DEFUN onChange ()
  (SETQ Control.NumChanges (CHANGES))
)
```

In the above example '`Control.NumChanges`' could be a virtual attribute somewhere in an 'exactly-one-record' table for displaying the project's number of changes.

See also `onOpen`, `onClose`, `onAdminMode`, `logLabel`, `demo Trigger.mb`.

16.29.6 logLabel

When creating a new entry for the project's log, MUIbase searches the project's program for a function with the name `logLabel`. If it exists, it calls this function without any arguments. The returned expression is converted to a string and used for the `'_Label'` field of the new log entry (see Section 8.3 [Set log label], page 39).

Example

```
(DEFUN logLabel ()
  Control.CurrentUser.Name
)
```

The above example has been taken from the `Users.mb` project. Here the label is the name of the current user who opened the project. This means that all changes by the current user are tagged with his or her name. Thus, it is later possible to identify which user performed which change.

See also `onChange`, demo `Users.mb`.

16.29.7 mainWindowTitle

If a project's program contains a function with the name `mainWindowTitle` then the result of this function is used for setting the window title of the project's main window. The function is called without any arguments and should return a string value. The window title is automatically re-computed whenever an attribute used in the function changes.

In case `mainWindowTitle` does not exist, the window title shows the project's name.

Note that, in any case, MUIbase prepends the title with a `'*` character whenever the project has any unsaved changes.

See also demo `Trigger.mb`.

16.29.8 New Trigger

When the user wants to allocate a new record by selecting one of the menu items `'New record'` or `'Duplicate record'` and the `'New'` trigger of that table has been set to a MUIbase program function then this trigger function is executed. The `'New'` trigger function can be set in the table dialog (see Section 15.1.1 [Creating tables], page 59).

The trigger function receives `NIL` or a record pointer as the first and only argument. `NIL` means that the user wants to allocate a new record, a record pointer means that the user wants to duplicate this record. If the trigger function has more than one argument then these are initialized with `NIL`. The trigger function should allocate the new record by calling the `NEW` function (see Section 16.18.1 [NEW], page 126). The result returned by the trigger function will be examined. If it returns a record pointer then this record will be displayed.

The `'New'` trigger is also called when a MUIbase program calls the `NEW*` function (see Section 16.18.2 [NEW*], page 126).

Sample New trigger function

```
(DEFUN newRecord (init)
  (PROG1
    ; for returning the result of NEW
```



```

        (NEW Table init)
        ...
    )
)

```

See also NEW, NEW*, Delete trigger.

16.29.9 Delete Trigger

When the user wants to delete a record by selecting menu item ‘Delete record’ and the ‘Delete’ trigger of that table has been set to a MUIbase program function then this trigger function is executed. The ‘Delete’ trigger function can be set in the table dialog (see Section 15.1.1 [Creating tables], page 59).

The trigger function receives a Boolean argument as its only argument. If the argument is non-NIL then the function should ask the user if he really wants to delete the record. If so, the function should call DELETE (see Section 16.18.3 [DELETE], page 126) for deleting the record.

The ‘Delete’ trigger is also called when a MUIbase program calls the DELETE* function (see Section 16.18.4 [DELETE*], page 127).

Sample Delete trigger function

```

(DEFUN deleteRecord (confirm)
  (DELETE Table confirm)
)

```

See also DELETE, DELETE*, New trigger.

16.29.10 Comparison Function

For defining an order on the records of a table you can use a comparison function. See Section 11.4 [Changing orders], page 47, for information on how to specify such a function for a table. The function takes two record pointers as arguments and returns an integer value reflecting the order relation of the two records. The comparison function should return a value smaller than 0 if its first argument is smaller than the second, 0 if they are equal and a value larger than 0 if the first argument is greater than the second one.

For example, if you have a table ‘Persons’ with a string attribute ‘Name’ then you could use the following function for comparing two records:

```

(DEFUN cmpPersons (rec1:Persons rec2:Persons)
  (CMP rec1.Name rec2.Name)
)

```

This will order all records according to the ‘Name’ field using case sensitive string comparison. Note that by using an attribute list you could not archive the same ordering as string comparison is done case insensitive for attribute lists.

Using a comparison function you can define very complex order relations. Be careful not to create recursive functions that will call itself. MUIbase will stop program execution and prompt you with an error message if you try to do so. Also you should not use commands that cause side effects, e.g. setting a value to an attribute.

When using a comparison function, MUIbase does not always know when it has to reorder its records. E.g. consider in the above example another table ‘Toys’ with a string

attribute 'Name' and a reference attribute 'Owner' referring to 'Persons', and the following function for comparing records:

```
(DEFUN cmpToys (rec1:Toys rec2:Toys)
  (CMP* rec1.Owner rec2.Owner)
)
```

This function is using the order of 'Persons' for determining the order of the records, thus the records of 'Toys' are sorted according to the order of 'Persons'.

Now if the user changes one record in the 'Persons' table and this record gets a new position then also records in 'Toys' that refer to this record have to be reordered. MUIbase, however, does not know of this dependency.

Besides using menu item 'Table - Reorder all records' on the 'Toys' table for rearranging the order, you can implement an automatic reordering yourself by specifying the following trigger function for the 'Name' attribute of 'Persons':

```
(DEFUN setName (newValue)
  (SETQ Persons.Name newValue)
  (FOR ALL Toys WHERE (= Toys.Owner Persons) DO
    (SETISSORTED Toys NIL)
  )
  (REORDER Toys)
)
```

The function clears the sorted flag for all records that refer to the current record of table 'Persons' and then reorders all unsorted records of table 'Toys'.

See also Order, CMP, GETISSORTED, SETISSORTED, REORDER, REORDERALL, GETORDERSTR, SETORDERSTR, demo `Order.mb`.

16.29.11 Attribute Trigger

In the attribute dialog (see Section 15.2.1 [Creating attributes], page 61) you can define a trigger function that is called whenever the user wants to change the attribute contents.

If you have defined such a trigger function for an attribute and the user changes the value of that attribute then the record contents are not automatically updated with the new value. Instead the value is passed to the trigger function as first argument. The trigger function can now check the value and may refuse it. To store the value in the record you have to use the SETQ function.

The trigger function should return the result of the SETQ call or the old value of the attribute if it decides to refuse the new one.

The trigger function is also called when a MUIbase program calls the SETQ* function (see Section 16.6.5 [SETQ*], page 84) for setting a value to the attribute.

Sample attribute trigger function

```
(DEFUN setAmount (amount)
  (IF some-expression
    (SETQ Table.Amount amount)
    (ASKBUTTON NIL "Invalid value!" NIL NIL)
  )
)
```

```

    Table.Amount                ; return current value
)

```

See also SETQ*

16.29.12 Programming Virtual Attributes

In MUIbase virtual attributes are special attributes that calculate their value on the fly whenever it is needed. E.g. if you go to another record by clicking on one of the arrow buttons in a table's panel bar then a virtual attribute in that table is automatically recomputed and displayed (given appropriate settings for the virtual attribute, see Section 15.3.3 [Attribute object editor], page 66). For computing the value the attribute's 'Compute' trigger function is called. This trigger function can be specified in the attribute dialog (see Section 15.2.2 [Type specific settings], page 61). The return value of this function defines the value of the virtual attribute. If you don't specify a 'Compute' trigger function for a virtual attribute then the attribute's value is NIL.

You can also trigger the calculation of a virtual attribute by simply accessing it in an MUIbase program, so e.g. if you have a button that should compute the value of the virtual attribute, you only need to specify a function for the button like the following one:

```

(DEFUN buttonHook ()
  virtual-attr
)

```

You can also set a virtual attribute to any value by using the SETQ function:

```

(SETQ virtual-attr expr)

```

However if you access the virtual attribute after the SETQ call then the value of the virtual attribute is recomputed.

There is no caching of the value of a virtual attribute because it's not easy to know when the value has to be recomputed and when not. Thus you should access virtual attributes rarely and cache the value in local variables for further use by yourself.

For an example on how to use virtual attributes please check the `Movie.mb` demo.

See also Virtual, demo `Movie.mb`.

16.29.13 Compute Enabled Function

For attribute objects and window buttons you can specify a trigger function for computing the enabled state of the object. See Section 15.3.3 [Attribute object editor], page 66, and Section 15.3.10 [Window editor], page 72, for information on how to specify this trigger function.

The trigger function is called without any arguments. It should return NIL for disabling the object and non-NIL for enabling it.

For example the compute enabled function for an object, that gets enabled when a certain virtual attribute using the 'List' kind has an active item, could look like this:

```

(DEFUN enableObject ()
  (GETVIRTUALLISTACTIVE virtual-list-attr)
)

```

See also Attribute object editor, Window editor, demo `Users.mb`.

16.29.14 Compute Record Description

For table objects and attribute objects of type reference, a trigger function can be entered for computing a record description (see Section 15.3.2 [Table object editor], page 65, and Section 15.3.3 [Attribute object editor], page 66).

The trigger function is called without any arguments. It should return a single expression or a list of expressions.

For example, in a table ‘Person’ with attributes ‘Name’ and ‘Birthday’, the function could look like this:

```
(DEFUN personDescription ()
  (LIST Person.Name Person.Birthday)
)
```

See also Table object editor, Attribute object editor.

16.29.15 Double Click Trigger

For virtual attributes that use the list kind for displaying its contents, a trigger function can be specified which gets called whenever the user double clicks on an item in the list. See Section 15.3.3 [Attribute object editor], page 66, for information on how to specify this trigger function for a virtual attribute object.

The trigger functions is called with three arguments. The first argument holds the row number of the clicked field, starting with 1 for the first line (row 0 refers to the list header). The second argument holds the column number starting with 0. The third argument is a pointer to the record the list field has been generated from, or NIL if the entry has not been generated directly from one. The return code of the function is ignored.

A typical example of a double click trigger is the following.

```
(DEFUN doubleClickTrigger (row col rec:Table)
  ...
)
```

Here *rec* is declared as a record pointer to *Table*. This way attributes of *Table* can be accessed directly from *rec*.

In case there is more than one possible table the record argument could belong to, the following construction using type predicates to different tables is useful.

```
(DEFUN doubleClickTrigger (row col rec)
  (COND
    ((RECP Table1 rec) (SETQ Table1 rec) ...)
    ((RECP Table2 rec) (SETQ Table2 rec) ...)
    ...
  )
)
```

The list item the user clicked on might not be related to any record. In this case, the third argument can be ignored and the list element be accessed like in the following example.

```
(DEFUN doubleClickTrigger (row col)
  (PRINT (NTH col (NTH row virtual-attr)))
)
```

See also Attribute object editor, demo *Movie.mb*.

16.29.16 Compute Listview Labels

For string attributes, the GUI object can contain a listview pop-up that when pressed opens a list of label strings the user can choose from. The labels in this list can be static labels or they can be computed by a trigger function. See Section 15.3.3 [Attribute object editor], page 66, for information on how to select between static and computed labels and how to specify the trigger function.

The trigger function for computing the labels does not have any arguments. It should return a memo text with one label per line or NIL for no labels.

For example the compute function could look like this:

```
(DEFUN computeLabels ()
  "Tokyo\nMunich\nLos Angeles\nRome"
)
```

See also Compute reference records, Attribute object editor.

16.29.17 Compute Reference Records

For reference attributes, the GUI object usually contains a pop-up button that when pressed opens a list of records the user can choose from. The list of records in this pop-up can be computed by a trigger function. See Section 15.3.3 [Attribute object editor], page 66, for information on how to specify the trigger function for reference fields.

The function for computing the list of records does not have any arguments. It should return a list that is searched for the occurrence of records of the referenced table. Any such record found is added to the list shown in the reference pop-up. Items that are not records of the referenced table are ignored silently.

A typical compute function for reference records is the following example. Say a project contains a table 'Person' with a Boolean attribute 'Female'. Then the following compute function only shows the female persons in the reference popup:

```
(DEFUN computeFemaleRecords ()
  (SELECT Person FROM Person WHERE Female)
)
```

See also Compute list-view labels, Attribute object editor.

16.30 List of Obsolete Functions

The following functions are obsolete starting with MUIbase version 2.7.

- GETDISABLED
- SETDISABLED
- GETWINDOWDISABLED
- SETWINDOWDISABLED

Obsolete functions are not working as expected any longer and calling any of them is either ignored (resulting in a no-operation), opens a warning dialog, or causes an error, depending on the setting of menu item 'Program - Obsolete functions' (see Section 7.2.9 [Obsolete functions], page 36).

It is recommended to remove these functions from a project program and implement the functionality using the enabled/disabled setting of attribute objects and window buttons (see Section 16.29.13 [Compute enabled function], page 149).

17 ARexx Interface

The ARexx interface is only available in the MUIbase version for Amiga.

ARexx is a standard interface for Amiga programs to enable access to functions and data from other programs. MUIbase provides such an ARexx port with a small but well defined set of commands that enable an external program to virtually compute everything a MUIbase program can compute. Furthermore MUIbase' ARexx interface implements a transaction mechanism similar to other relational databases.

Example ARexx scripts for MUIbase can be found in the 'rexx' directory.

17.1 Port Name

The port name of the MUIbase ARexx port is 'MUIbase.n' where *n* is a counter starting with 1. Usually, if you start MUIbase only once, the port name is 'MUIbase.1'.

You need the port name in the ARexx `address` statement before calling any of MUIbase' ARexx commands. The following program fragment shows how to check for the presence of a MUIbase ARexx port, start MUIbase if needed, and address the port.

```
if ~show(ports, MUIbase.1) then
do
  address command 'run <nil: >nil: MUIbase:MUIbase -n'
  address command 'waitforport MUIbase.1'
end

address MUIbase.1
```

See also sample ARexx script `address.rexx`.

17.2 Command Syntax

After addressing the MUIbase ARexx port you can call any of MUIbase' ARexx commands. The syntax is the same as for most other implementations:

```
cmd [arg1 ...]
```

where *cmd* is one of the commands described further down in this chapter, and *arg1* ... are optional arguments to the command.

Since the ARexx interpreter evaluates the command line before sending it to MUIbase, it is sometimes useful to quote some or all of the arguments. It is recommended to use single quotes (') around arguments which should not be further evaluated by the ARexx interpreter. This way you can still place double quotes ("), e.g. for string constants, in the arguments. Furthermore you can integrate the value of ARexx variables by unquoting them. Here is an example using MUIbase' `eval` command.

```
search = ''
eval handle 'select Name from Person where (like Name "*"search"*")'
```

See also 2ARexx `eval, Eval`.

17.3 Return Codes

After calling one of MUIbase' ARexx commands several ARexx variables are updated with the result of the command. For reading all of the results of a command you should enable the ARexx results option by adding the following line at the beginning of your ARexx script.

```
options results
```

There are 3 ARexx variables that can be set by the MUIbase ARexx interface: *rc*, *results*, and *lasterror*. Variable *rc* is always set and reflects the success or failure of a command. If a command was successful, *results* holds the actual result of the command, whereas in the case of an unsuccessful command, *lasterror* can hold additional information describing the error.

For variable *rc* the following return codes exist:

Return code Meaning

0	Success. Variable <i>result</i> holds the actual result.
-1	Implementation error. Should never happen.
-2	Out of memory.
-3	Unknown ARexx command.
-4	Syntax error.
<= -10	Other error. Error description can be found in <i>lasterror</i> .
-12	Compilation error (only for compile command).

Note that only for *rc* <= -10 variable *lasterror* holds a valid error description. In the future more error codes might be added to enable a more detailed error handling.

Here is a typical code fragment showing how to examine the result of a MUIbase ARexx command.

```
eval handle 'select * from Accounts'
if (rc == 0) then
  say result
else if (rc == -1) then
  say "Implementation error"
else if (rc == -2) then
  say "Out of memory"
else if (rc == -3) then
  say "Unknown command"
else if (rc == -4) then
  say "Command syntax error"
else if (rc <= -10) then
  say lasterror
else
  say "Error: " rc
```


17.4 Quit

The `quit` command causes MUIbase to exit. See also the MUI documentation.

17.5 Hide

Command `hide` iconifies all open MUIbase windows. See also the MUI documentation.

17.6 Show

Command `show` deiconifies MUIbase and reopens the windows. See also the MUI documentation.

17.7 Info

The `info` command provides information about title, author, copyright, description, version, base and screen of a MUI application.

Command	Value of <i>result</i>
<code>info title</code>	Title of application
<code>info author</code>	Author of application
<code>info copyright</code>	Copyright message
<code>info description</code>	Short description
<code>info version</code>	Version string
<code>info base</code>	Name of ARexx port
<code>info screen</code>	Name of public screen

See also the MUI documentation.

17.8 Help

The `help` command writes a file containing all available ARexx commands of a MUI application.

```
help filename
```

ARexx commands are listed using the AmigaDos command line syntax. See the MUI documentation for more information and your AmigaDos manual for the command line syntax.

17.9 Compile

The `compile` command compiles an external program source file.

```
compile source [update]
```

The command compiles the external program source of the project whose external source filename points to the same file as *source*. On success, the command returns 0 and, if `update` has been specified, re-writes the external source file. Updating the source file allows to pretty

print the MUIbase keywords. A successfully compiled program is then used as the project's program and used when executing trigger functions.

If compilation fails, an error code of -12 is returned and *lasterror* is set to a string containing 4 lines:

- The first line holds the name of the file the error occurred.
- The second line holds the error line number starting with 1.
- The third line holds the error column starting with 1.
- The fourth line describe the error in readable text.

Note that a project must have already been opened before sending the `compile` command for compiling its external source. In case no project whose external source file points to *source* is found, an error code ≤ -10 (but different from -12) is returned and *lasterror* is set.

17.10 Connect

The `connect` command opens the communication to a MUIbase project.

```
connect project-name [GUI]
```

The command first checks if the project specified by `project-name` has already been opened and loads it if needed. A project is only opened once and multiple connections to the same project share the access to the database. Next a unique communication handle is generated. A communication handle is an integer value not equal to zero. If the keyword `GUI` has been added to the command line then also the graphical user interface of the MUIbase project is opened. Otherwise no graphical user interface is generated allowing to process MUIbase ARexx commands in the background without direct user interaction.

On success, the command returns 0 and sets *result* to the value of the handle.

Example: `'connect "MUIbase:Demos/Movies.mb"'` establishes a connection to the sample movie database.

See also 2ARexx `disconnect, Disconnect`, 2ARexx `connections, Connections`, 2ARexx `return codes, Return codes`.

17.11 Disconnect

The `disconnect` command closes an existing connection.

```
disconnect handle
```

Closes the database connection given in *handle*. If this was the only connection to the project *handle* refers to and there is no graphical user interface for the project then the project is closed and removed from memory. Otherwise the project stays open.

Example: `'disconnect 1'` closes connection with handle value 1.

See also 2ARexx `connect, Connect`, 2ARexx `connections, Connections`, 2ARexx `return codes, Return codes`.

17.12 Connections

To find out about existing connections, use the `connections` command.

```
connections
```

On success, `connections` returns 0 and sets *result* to a readable string where each line shows a connection consisting of handle value and project name.

Example: the *result* variable after a `connections` call could look like the following:

```
3 MUIbase:Demos/Accounts.mb
5 MUIbase:Demos/Movies.mb
6 MUIbase:Demos/Movies.mb
7 MUIbase:Demos/Movies.mb
```

See also 2ARexx `connect,Connect`, 2ARexx `disconnect,Disconnect`, 2ARexx `return codes,Return codes`.

17.13 Eval

The main interface of MUIbase' ARexx port for retrieving and updating data is through the `eval` command.

```
eval handle lisp-cmd
```

The `eval` command interprets the given command *lisp-cmd* (written in MUIbase' lisp language) on the project specified by *handle*. A handle can be obtained by the `connect` command. The command *lisp-cmd* can be any expression of MUIbase' programming language. Optionally the outermost parenthesis around the expression can be omitted. It is recommended to surround *lisp-cmd* by single quotes as described in Section 17.2 [Command syntax], page 153.

If successful, `eval` returns 0 and sets *result* to a string representation of the return value of *lisp-cmd*. The string representation is done in a way that still allows to find out what kind of data is returned, e.g. strings are surrounded by double quotes and lists are surrounded by parenthesis with items separated by spaces or newline characters. If you want to ensure a certain format, use your own formatting withing the specified lisp command.

If you did changes to the database within the `eval` command and did not start a transaction first (see Section 17.14 [Transaction], page 158) then the changes are automatically made permanent (auto commit). Otherwise (you did start a transaction before calling `eval`) the changes are kept in memory until a `commit` command makes them permanent or a `rollback` command undoes the changes.

Example:

```
options results
address MUIbase.1
connect "MUIbase:Demos/Movie.mb"
if rc = 0 then
do
    handle = result
    eval handle 'select Title, Director from Movies'
end
if rc = 0 then
```

```
say result
```

The output of the above example could look like this:

```
( ( "Title" "Director" )
  ( "Batman" "Tim Burton" )
  ( "Batman Returns" "Tim Burton" )
  ( "Speechless" "Ron Underwood" )
  ( "Tequila Sunrise" "Robert Towne" )
  ( "Mad Max" "George Miller (II)" )
  ( "Braveheart" "Mel Gibson" )
  ( "2010" "Peter Hyams" ) )
```

See also 2ARexx connect,Connect, 2ARexx command syntax,Command syntax, 2ARexx return codes,Return codes, 2ARexx transaction,Transaction, 2ARexx commit,Commit, sample ARexx script movies.rexx.

17.14 Transaction

MUIbase' ARexx port allows to do transactions on a database. A transaction is a set of commands to a database (allowing modifications of data in the database) that is either executed and made permanent completely (**commit**) or withdrawn at any point within the transaction (**rollback**). A transaction can be started by issuing the following command:

```
transaction handle
```

where *handle* refers to a project as obtained by the **connect** command (see Section 17.10 [Connect], page 156).

After issuing a **transaction** command you can put as many **eval** commands as you like without actually changing the database. At some point, however, you have to decide if you want to make changes permanent (see Section 17.15 [Commit], page 158) or to go back to the state before issuing the **transaction** command (see Section 17.16 [Rollback], page 159).

After issuing a **transaction** command, access to the corresponding project is made exclusive to the specified handle. Thus other programs trying to access the database including the user accessing MUIbase by its graphical user interface are blocked (or delayed in case of another ARexx connection) until the exclusive access is released by calling the **commit** or **rollback** command.

Usually the **transaction** command returns 0. In case another ARexx connection gained exclusive access to the same project as *handle* refers to, the call is blocked until the other connection finished by committing or rolling back the database.

See also 2ARexx eval,Eval, 2ARexx commit,Commit, 2ARexx rollback,Rollback, 2ARexx return codes,Return codes.

17.15 Commit

The **commit** command is used at the end of a transaction to make changes permanent.

```
commit handle
```

The **commit** command ends a transaction (see Section 17.14 [Transaction], page 158) by saving the project the argument *handle* refers to. On success, **commit** returns 0. If you did

not start a transaction before calling `commit` or if some other error occurs a value not equal to 0 is returned.

See also 2ARexx `rollback`, `Rollback`, 2ARexx `transaction`, `Transaction`, 2ARexx `return codes`, `Return codes`.

17.16 Rollback

To cancel changes made in a transaction use the `rollback` command.

`rollback` *handle*

All changes made in the project referred to by *handle* since the beginning of the current transaction (see Section 17.14 [`Transaction`], page 158) are withdrawn and the state of the project before the transaction is restored. If successful `rollback` returns 0.

See also 2ARexx `commit`, `Commit`, 2ARexx `transaction`, `Transaction`, 2ARexx `return codes`, `Return codes`.

Menus

Menu Project

- Info** Information about a project, see Section 6.2 [Info], page 28.
- New** Starts a new project, see Section 6.3 [New project], page 28.
- Clear - Project**
Resets a project, see Section 6.4 [Clear project], page 28.
- Clear - Records**
Deletes all records, see Section 6.4 [Clear project], page 28.
- Open - Project**
Loads a project, see Section 6.5 [Open project], page 29.
- Open - Demo**
Loads a demo project, see Section 6.5 [Open project], page 29.
- Reload** Reload new version of project, see Section 6.5 [Open project], page 29.
- Revert to saved**
Reload project when it was saved last, see Section 6.6 [Save project], page 29.
- Save** Saves project to disk, see Section 6.6 [Save project], page 29.
- Save & reorg**
Saves and reorganizes a project, see Section 6.6 [Save project], page 29.
- Save & reorg as**
Saves and reorganizes with new filename, see Section 6.6 [Save project], page 29.
- Change to admin mode**
Restricting access to project structure, see Section 6.7 [Admin and user mode], page 30.
- Change admin password**
Authentication for admin mode, see Section 6.7 [Admin and user mode], page 30.
- Check data integrity**
If your project ever gets corrupted, see Section 6.8 [Check data integrity], page 30.
- Swap records**
Flush all records to disk, see Section 6.9 [Swap records], page 30.
- Structure editor**
Open structure editor, see Chapter 15 [Structure editor], page 59.
- Export structure**
Overview of all tables and attributes, see Section 15.4 [Export structure], page 73.
- Close** When your are done with a project, see Section 6.10 [Close project], page 31.

Save & Close

Saves then closes project, see Section 6.10 [Close project], page 31.

Quit

Exit MUIbase, see Chapter 3 [Getting started], page 5.

Menu Preferences

User settings

Global settings stored in user environment, see Section 7.1 [User settings], page 32.

Formats

Real and date formats, see Section 7.1.1 [Formats], page 32.

External editor

Specify your external editor, see Section 7.1.2 [External editor], page 32.

External viewer

Specify your external viewer, see Section 7.1.3 [External viewer], page 33.

Extra buttons in Tab chain

Include extra buttons in the Tab chain, see Section 7.1.4 [Extra buttons in Tab chain], page 33.

Advance on <Enter>

Advance on Enter. Move to next field when pressing *Enter* key, see Section 7.1.5 [Advance on Enter], page 34.

Confirm quit

Confirmation dialog when quitting MUIbase, see Section 7.1.6 [Confirm quit], page 34.

MUI

MUI's preferences, see Section 7.1.7 [MUI], page 34.

Project settings

Settings stored with a project, see Section 7.2 [Project settings], page 34.

Record memory

Size of record buffer, see Section 7.2.1 [Record memory], page 34.

Confirm delete record

Confirmation dialog when deleting records, see Section 7.2.2 [Confirm delete record], page 35.

Paths relative to project

How relative path names are treated, see Section 7.2.3 [Paths relative to project], page 35.

Confirm auto reload

Confirmation dialog when auto-reloading a project, see Section 7.2.4 [Confirm auto reload], page 35.

Confirm save & reorg

Confirmation dialog when reorganizing a project, see Section 7.2.5 [Confirm save & reorg], page 35.

Save as default

Saves project settings for future projects, see Section 7.3 [Save as default], page 37.

Menu Log

Logging active

How to start and stop logging, see Section 8.2 [Activate logging], page 38.

Set log label

Setting a label for new log entries, see Section 8.3 [Set log label], page 39.

Import log

Importing log entries from a file, see Section 8.4 [Import log], page 39.

Export log

Exporting log entries to a file, see Section 8.5 [Export log], page 39.

Clear log Deleting all log entries, see Section 8.6 [Clear log], page 39.

View log How to view all log entries, see Section 8.7 [View log], page 39.

Menu Table

New record

Adding a new record, see Section 9.2 [Adding records], page 40.

Duplicate record

Copying a record, see Section 9.2 [Adding records], page 40.

Delete record

If you don't need a record any more, see Section 9.4 [Deleting records], page 42.

Delete all records

If you want to start from scratch, see Section 9.4 [Deleting records], page 42.

Goto Record

Browsing records, see Section 9.5 [Browsing records], page 43.

Change filter

Specify a filter expression, see Section 10.1.2 [Changing filters], page 44.

Change order

How to specify an order, see Section 11.4 [Changing orders], page 47.

Reorder all records

If records ever become unsorted, see Section 11.5 [Reorder all records], page 48.

Search for How to search for a record, see Section 12.1 [Search dialog], page 49.

Search forward

Go to the next matching record, see Section 12.2 [Forward/backward search], page 49.

Search backward

Go to the previous matching record, see Section 12.2 [Forward/backward search], page 49.

Import records

How to import records, see Section 13.3 [Importing records], page 52.

Export records

How to export records, see Section 13.4 [Exporting records], page 52.

View all records

Listing all records of a table, see Section 9.6 [View all records], page 43.

Menu Program

Edit Where to enter a MUIbase program, see Section 16.1 [Program editor], page 74.

Compile Compiling a program, see Section 16.1 [Program editor], page 74.

Program source

Internal or external program source, see Section 7.2.6 [Program source], page 35.

Cleanup external program source

Delete external source files when no longer needed, see Section 7.2.7 [Cleanup external program source], page 36.

Embed debug information

Compile with or without debug information, see Section 7.2.8 [Program debug information], page 36.

Obsolete functions

How to handle calls of obsolete functions, see Section 7.2.9 [Obsolete functions], page 36.

Sort trigger functions

Alphabetical sorting in pop-up windows, see Section 7.2.10 [Sort trigger functions], page 36.

Include directory

Where to look for external include files, see Section 7.2.11 [Program include directory], page 37.

Output file

Where program output goes, see Section 7.2.12 [Program output file], page 37.

Queries Open the query editor, see Section 14.2 [Query editor], page 53.

Menu Help

Contents This user manual.

About About MUIbase, see Chapter 1 [Copying], page 1.

About MUI

About the Magic User Interface, see Section 1.5 [Third party material], page 1.

Acknowledgments

Thanks to:

- Ralph Reuchlein (Ralphie) for bug reports, ideas and suggestions, and for the German translation of the MUIbase user manual.
Ralphie also created and maintains the MUIbase home page <http://muibase.sourceforge.net>.
- Pascal Marcelin for his believe in MUIbase and Amiga, and for the first web server connecting to MUIbase through its ARexx interface.
- Christoph Pölzl and Sébastien Pölzl for the artwork used in MUIbase, the PNG icon set and for testing on MorphOS.
- Alexandre Balaban for the French translation of the user manual (with great help from Lionel Muller and Gilles Mathevet) and for porting MUIbase to AmigaOS 4.
- Stéphane Aulery for continuing the French translation and updating the web pages.
- Harold Kinds for the new ImportSample project.
- Ilkka Lehtoranta for completing the port to MorphOS.
- Thomas Fricke and Adrian Maleska for various graphics improving the appearance of MUIbase.
- Martin Merz for his Mason icons.
- Mats Granstrom for beta testing of MUIbase and for writing the tutorial.
- John Hertig, Harold Kinds, Magnus Hammarstrom, Henning Thilemann, Joseph Durchalet, André Schenk, Klaus Gessner, and Oliver Roberts for ideas and beta-testing.
- Jernej Simoncic for permission to use his Windows install script for The Gimp as basis for the install script for MUIbase for Windows.

Author

MUIbase is developed by:

Steffen Gutmann

Email: muibase@yahoo.com

Function Index

#

#define	75
#elif	76
#else	77
#endif	77
#if	76
#ifdef	76
#ifndef	76
#include	75
#undef	75

*

*	97
---------	----

+

+	96
---------	----

-

-	97
---------	----

/

/	97
---------	----

<

<	94
<*	94
<=	94
<=*	94
<>	94
<>*	94

=

=	94
=*	94

>

>	94
>*	94
>=	94
>=*	94

1

1+	97
1-	97

A

ABS	98
ADDMONTH	112
ADDYEAR	113
ADMINPASSWORD	137
AND	93
APPEND	115
APPLY	85
ASC	106
ASKBUTTON	119
ASKCHOICE	117
ASKCHOICESTR	118
ASKDIR	116
ASKFILE	116
ASKINT	117
ASKMULTI	120
ASKOPTIONS	119
ASKSTR	117
ATTRNAME	129

C

CASE	85
CHANGES	136
CHR	106
CMP	95
CMP*	95
COMPLETE	140
COMPLETEADD	140
COMPLETMAX	139
CONCAT	105
CONCAT2	105
COND	86
CONS	113
CONSP	89
COPYREC	129
COPYSTR	105

D

DATE	92
DATEDMY	112
DATEP	89
DAY	111
DEFUN	81
DEFUN*	82
DEFVAR	82
DEFVAR*	83
DELETE	126
DELETE*	127
DELETEALL	127
DIRNAME	139
DIV	98
DO	87

DOLIST 87
 DOTIMES 86

E

EDIT 137
 EDIT* 137
 ERROR 89
 EXIT 88
 EXP 99

F

FCLOSE 122
 FEOF 124
 FERROR 123
 FFLUSH 126
 FGETCHAR 124
 FGETCHARS 124
 FGETMEMO 125
 FGETSTR 125
 FIELD 104
 FIELDS 104
 FILENAME 139
 FILLMEMO 110
 FIRST 114
 FOPEN 121
 FOR ALL 88
 FORMATMEMO 111
 FPRINTF 123
 FPUTCHAR 125
 FPUTMEMO 125
 FPUTSTR 125
 FSEEK 124
 FTELL 124
 FUNCALL 85

G

GC 140
 GETADMINMODE 136
 GETDISABLED 151
 GETFILTERACTIVE 132
 GETFILTERSTR 132
 GETISSORTED 128
 GETLABELS 129
 GETMATCHFILTER 127
 GETORDERSTR 130
 GETVIRTUALLISTACTIVE 135
 GETWINDOWDISABLED 151
 GETWINDOWOPEN 134

H

HALT 89

I

IF 85
 INDENTMEMO 111
 INDEXBRK 101
 INDEXBRK* 101
 INDEXSTR 101
 INDEXSTR* 101
 INSMIDSTR 101
 INT 91
 INTP 89

L

LAST 114
 LEFTSTR 100
 LEN 100
 LENGTH 114
 LET 83
 LIKE 107
 LINE 109
 LINES 109
 LIST 114
 LISTP 89
 LISTTOMEMO 110
 LISTTOSTR 105
 LOG 99
 logLabel 146
 LOWER 106

M

mainWindowTitle 146
 MAPFIRST 115
 MAX 95
 MAX* 95
 MAXLEN 129
 MEMO 91
 MEMOP 89
 MEMOTOLIST 110
 MESSAGE 139
 MIDSTR 100
 MIN 96
 MIN* 96
 MOD 98
 MONTH 111
 MONTHDAYS 112

N

NEW 126
 NEW* 126
 NEXT 88
 NOT 94
 NOW 113
 NTH 114
 NULL 89

O

onAdminMode	145
onChange	145
onClose	145
onOpen	144
onReload	144
OR	94

P

POW	99
PREPARECHANGE	136
PRINT	123
PRINTF	123
PROG1	83
PROGN	83
PROJECTNAME	135
PUBSCREEN	140

R

RANDOM	98
REAL	92
REALP	89
RECNUM	128
RECORD	133
RECORDS	133
RECP	89
REMHARS	103
REORDER	131
REORDERALL	131
REPLACESTR	102
REPLACESTR*	102
REST	114
RETURN	89
REVERSE	115
RIGHTSTR	100
RINDEXBRK	102
RINDEXBRK*	102
RINDEXSTR	101
RINDEXSTR*	102
ROUND	98

S

SELECT	133
SETADMINMODE	136
SETBGPEN	134
SETCURSOR	134
SETDISABLED	151
SETFILTERACTIVE	132
SETFILTERSTR	132
SETISSORTED	128
SETLABELS	130

SETMATCHFILTER	128
SETMIDSTR	100
SETORDERSTR	130
SETQ	84
SETQ*	84
SETVIRTUALLISTACTIVE	135
SETWINDOWDISABLED	151
SETWINDOWOPEN	135
SHA1SUM	106
SORTLIST	115
SORTLISTGT	116
SPRINTF	107
SQRT	99
STAT	138
stdout	122
STR	90
STRP	89
STRTOLIST	104
SYSTEM	138
SYSTEM*	138

T

TABLERNAME	130
TACKON	138
TIME	93
TIMEP	89
TODAY	113
TRIMSTR	103
TRUNC	98

U

UPPER	106
-------------	-----

V

VIEW	137
VIEW*	137

W

WORD	103
WORDS	103

Y

YEAR	111
YEARDAYS	112

Concept Index

1

- 1:1 relationships 23
- 1:n relationships 23

A

- Accessing record contents 78
- Acknowledgments 164
- Activate logging 38
- Active object 40
- Active table 40
- Admin mode 30
- Admin password 30
- Advance on Enter 34
- Amiga version 2
- ARexx 153
- ARexx command syntax 153
- ARexx commit 158
- ARexx compile 155
- ARexx connect 156
- ARexx connections 157
- ARexx disconnect 156
- ARexx eval 157
- ARexx help 155
- ARexx hide 155
- ARexx info 155
- ARexx port name 153
- ARexx quit 155
- ARexx return codes 154
- ARexx rollback 159
- ARexx show 155
- ARexx transaction 158
- Attribute functions 129
- Attribute management 60
- Attribute object editor 66
- Attribute objects 26
- Attribute trigger 148
- Attribute types 19
- Attribute types (table) 22
- Attributes 19
- Author 165

B

- Balance objects 27
- BetterString 2
- Boolean attributes 20
- Boolean functions 93
- Browsing records 43
- Buttons 21

C

- Change filter 44
- Change order 47
- Changing attributes 63
- Changing tables 60
- Check data integrity 30
- Choice attributes 20
- Cleanup external program source 36
- Clear log 39
- Clear project 28
- Close project 31
- Command syntax 81
- Comparison function 147
- Comparison functions 94
- Compute enabled function 149
- Compute list-view labels 151
- Compute record description 150
- Compute reference records 151
- Confirm auto reload 35
- Confirm delete record 35
- Confirm quit 34
- Confirm save & reorg 35
- Constants 80
- Copying attributes 63
- Copying MUIbase 1
- Corrupted database 30
- Creating attributes 61
- Creating tables 59

D

- Data retrieval 53
- Data types for programming 79
- Date attributes 20
- Date functions 111
- Defining commands 81
- Delete record 42
- Delete trigger 147
- Deleting attributes 63
- Deleting tables 60
- Disclaimer 1
- Display field 64
- Display management 64
- Donation 1
- Double click trigger 150
- Duplicate record 40

E

Empty order	46
Entering Boolean Values	41
Entering Choice Values	41
Entering Date Values	41
Entering Integer Values	41
Entering NIL value	42
Entering Reference Values	42
Entering Time Values	41
Export log	39
Export queries as PDF	55
Export queries as text	54
Export records	52
Export structure	73
External editor	32
External program source	74
External viewer	33
Extra buttons in Tab chain	33

F

File format	28
File format for import and export	51
Filename attributes	19
Filename conventions	7
Filter	44
Filter examples	45
Filter expression	44
Font-name attributes	19
Formats	32
Forward/backward search	49
Function triggering	144
Functional parameters	142

G

Group editor	71
Groups	27
GUI functions	134

I

I/O functions	121
Icons	2
Image attributes	19
Image editor	71
Images	27
Import and Export	51
Import file example	51
Import log	39
Import records	52
Info	28
Initial record	19
Input requesting functions	116
Installing MUIbase on Amiga	6
Installing MUIbase on Linux	5
Installing MUIbase on Mac OS	5
Installing MUIbase on Windows	5

Integer attributes	20
Internal errors in database	30

K

Kinds of programs	78
-------------------------	----

L

Label editor	62
License	1
Linux version	2
Lisp syntax	77
List functions	113
List of obsolete functions	151
Log	38
Log table	38
logLabel	146

M

Mac OS version	2
Mailing list	1
Main window	26
mainWindowTitle	146
Many to many relationships	24
Masks	26
Mathematical functions	96
Memo attributes	21
Memo Context menu	41
Memo functions	109
Memory consumption	22
Menu Help	163
Menu Log	162
Menu Preferences	161
Menu Program	163
Menu Project	160
Menu Table	162
Menus	160
MUI	2
MUI preferences	34

N

n:m relationships	24
Name conventions for program symbols	78
New attribute	61
New project	28
New record	40
New table	59
New trigger	146
NList	2

O

Obsolete functions	36, 151
onAdminMode	145
onChange	145
onClose	145
One to many relationships	23
One to one relationships	23
onOpen	144
onReload	144
Open project	29
Order	46

P

Panel editor	65
Panels	26
Pre-defined constants	141
Pre-defined variables	141
Preferences	32
Preprocessing	75
Printing queries	55
Program control functions	83
Program debug information	36
Program editor	74
Program include directory	37
Program output file	37
Program source	35
Programming	74
Programming language	77
Programming virtual attributes	149
Project functions	135
Project settings	34
Projects	18

Q

Query editor	53
Query examples	56
Quitting MUIbase	7

R

Real attributes	20
Record filter	44
Record functions	126
Record memory	34
Record-editing	40
Records	19
Reference attributes	21
Reference filter	45
Register group editor	72
Register groups	27
Relational operators	94
Relationships	23
Relative paths	35
Reorder all records	48
Reorganization	29

S

Save as default	37
Save project	29
Search dialog	49
Search for	49
Search pattern examples	50
Select-from-where List Context Menu	42
Select-from-where queries	53
Semantics of expressions	143
Set log label	39
Sort trigger functions	36
Sorting attributes	64
Sorting tables	60
Space editor	71
Space objects	27
Starting MUIbase	6
String attributes	19
String functions	99
Structure editor	59
Swap records	30
System functions	137

T

Table functions	130
Table management	59
Table object editor	65
Tables	18
Tabular display	53
Text editor	70
Text objects	27
TextEditor	2
Third party material	1
Time attributes	20
Time functions	111
Tutorial	9
Type conversion functions	90
Type predicates	89
Type specific settings	61
Type specific settings for attribute objects	67
Type specifiers	142

U

Updating from a previous version	6
User interface	25
User mode	30
User settings	32

V

View all records	43
View log	39
Virtual attributes	21

W

Why lisp?.....	77
Window editor.....	72
Windows	26
Windows version.....	2